

Gary	Roger	S
AGE	Logic,	Inc.

This document contains reference pages for each XIElib function.

Revision History

Gary Rogers, AGE Logic, Inc., Public Review Draft, April, 1994

Syd Logan, NetManage, Inc., Minor technical edits, correction of errors, October, 1996

Copyright © 1994 AGE Logic, Inc.

Permission to use, copy, modify, distribute, and sell this documentation for any purpose is hereby granted without fee, provided that the above copyright notices and this permission notice appear in all copies. AGE Logic makes no representations about the suitability for any purpose of the information in this document. This documentation is only a draft standard of the X consortium and is therefore subject to change.

Acknowledgments

XIElib was provided by the X Consortium, with cooperation from AGE Logic, Inc. of San Diego, CA. It is a C subroutine library that provides a low level C binding of all features that are defined by Version 5.0 of the XIE Protocol.

Various parts of the text were borrowed from the Version 5.0 XIE Protocol Reference Manual, edited by Bob Shelley of AGE Logic, Inc.. Bob provided suggestions and comments that were invaluable in preparing this document. Dean Verheiden and Syd Logan, both of AGE Logic, Inc., graciously volunteered to review the original manuscript.

The author would like to thank Ralph Mor of the X Consortium for his careful review of this document. Ralph designed the XIElib and wrote its sample implementation, and his technical advice was indispensable. Adrian Nye, Editor for O'Reilly & Associates, Inc., provided substantive assistance in the preparation of this document, for which the author is very thankful.

Table of Contents

Introduction 1Startup FunctionsXieInitialize 3XieOueryTechniques 5XieCreateColorList 8XieD estrovColorList 9XiePurgeColorList 10XieQueryColorList11LUT FunctionsXieCreateLUT 12XieDestrovLUT 13Photomap 15XieQueryPhotoma FunctionsXieCreatePhotomap 14XieDestrovPhotomap 16ROI FunctionsXieCreateROI 18XieDestroyROI 19Photoflo 20XieDestrovPhotospace FunctionsXieCreatePhotospace 21XieExecuteImmed 22XieAllocatePhotofloGraph24XieCreatePhotoflo 25XieDestroyPhotoflo 27XieExecutePhotoflo 28XieModifvPhotoflo 29XieRedefinePhotoflo 31Xie OuervPhotoflo 32Client Data FunctionsXiePutClientData 34XieGetClientData 36Abort and Await FunctionsXieAbort 38XieAwait 39Photoflo Element FunctionsXieFloImportClientLUT 40XieFloImportClientPhoto 43XieFloImportClien 46XieFloImportDrawable 47XieFloImportDrawablePlane 49XieFloImpo rtLUT 51XieFloImportPhotomap 52XieFloImportROI 54XieFloArithmetic 55XieF 58XieFloBandExtract 60XieFloBandSelect 62XieFloBlen loBandCombine 63XieFloCompare 69XieFloConvertFromIndex 71XieF 66XieFloConstrain loConvertFromRGB 73XieFloConvertToIndex 75XieFloConvertToRGB 78XieF loConvolve 80XieFloDither 83XieFloGeometry 85XieFloLogical loMatchHistogram 91XieFloMath93XieFloPasteUp 95XieFloPoint97XieFloUnco 100XieFloExportClientLUT 102XieFloExp nstrain99XieFloExportClientHistogram ortClientPhoto 104XieFloExportClientROI 106XieFloExportDrawable 108Xie FloExportDrawablePlane 110XieFloExportLUT112XieFloExportPhotomap 114Xie FloExportROI 116Technique

FunctionsXieTecColorAllocAll 117XieTecColorAllocMatch 118XieTecColorAlloc 120XieTecRGBToCIELab 121XieTecRGBToCIEXYZ Requantize 123XieTecRG BToYCbCr 125XieTecRGBToYCC 127XieTecCIELabToRGB 129XieTecCIE XYZToRGB 132XieTecYCbCrToRGB 134XieTecYCCToRGB 136XieTecCli pScale 138XieTecConvolveConstant 140XieTecDecodeUncompressedSingle 141XieTecDecodeUncompressedTriple 143XieTecDecodeG31D 146XieTecDe 150XieTecDecodeTIFF2 152XieTecDe codeG32D 148XieTecDecodeG42D codeTIFFPackBits 154XieTecDecodeJPEGBaseline 156XieTecDecodeIPEGLossl 158XieTecDitherOrdered 160XieTecEncodeUncompressedSingle 161Xie ess TecEncodeUncompressedTriple 163XieTecEncodeG31D 166XieTecEncodeG3 2D 168XieTecEncodeG42D 170XieTecEncodeServerChoice 172XieTecEnc odeIPEGBaseline 174XieTecEncodeIPEGLossless 177XieTecEncodeTIFF2 179XieTecEncodeTIFFPackBits 181XieTecGeomAntialiasByArea 183XieTecGe omAntialiasByLowpass 185XieTecGeomGaussian 187XieTecGeomNearestNei ghbor 189XieTecHistogramGaussian 191XieTecHistogramHyperbolic 192Xie TecWhiteAdjustCIELabShift 194Free FunctionsXieFreeTechniques 195XieFreePhotofloGraph 196XieFreeEncodeJP **EGBaseline** 197XieFreeEncodeJPEGLossless 198XieFreePasteUpTiles 199XI Elib EventsColorAlloc EventEvents-1DecodeNotify Event Events-2ExportAvailable Event Events-3ImportObscured Event Events-4PhotofloDone Event Events-5XIElib ErrorsResource Errors Errors-1Photoflo Errors

Errors-2

Introduction

XIElib - Function Group

The following pages describe the format of the reference pages for each XIElib function. Every effort has been made to maintain consistency with the format used in Xlib Reference Manual for Version 11 (A. Nye, ed., O'Reilly & Associates, Inc., 1992). The reader is also referred to X Image Extension Protocol Reference Manual, Version 5.0 (R. Shelley, ed., 1994) for a complete definition of the XIE protocol.

Name

XieFunctionName - brief description of the function

Syntax

The Syntax section presents the calling syntax for the routine, including the declarations of the arguments and the return type. For example:

```
returntype XieFunctionName (arg1, arg2_ret)
    type1 arg1;
    type2 *arg2 ret;
```

Arguments

The Arguments section describes each of the arguments used by the function. There are two sorts of arguments: arguments to specify data to the function and arguments that return data from the function. An example of each type follows:

arg1 Specifies information for XieFunctionName. The

description for this type of argument always starts with

the word "Specifies."

arg2 ret Returns information from XieFunctionName. The

description for this type of argument always starts with

the word "Returns."

Returns

This section is present when XieFunctionName returns a value and describes what is returned.

Description

The Description section describes what the function does, what it returns, and what events or side effects it causes. It also may contain pertinent definitions, algorithms, and tables. A description of each XIE event structure is presented in the section XIElib Events.

Output Attributes

This section, which presents a table of element output attributes, is present if XieFloFunctionName specifies an element that produces output data.

Class Data class of output data

- single band (achromatic or index)

- triple band (trichromatic)

Type Data type

- constrained (quantization levels is Levels)

- unconstrained (quantization levels is unknown)

Width of output (in pixels per band)

Height of output (in pixels per band)

Levels Depends on type

- constrained: number of quantization levels

- unconstrained: unknown

Structures

The Structures section contains the C definitions of the XIE-specific data types used by XieFunctionName as arguments or return values. It also contains definitions of important constants used by the function.

Errors

The Errors section is present when an action of XieFunctionName could generate an error. A table of errors that can be generated and their causes is presented. The full list of errors is presented in the section XIElib Errors.

See Also

This section lists other functions that contain information related to XieFunctionName.

XIElib - Startup Functions

XieInitialize

Name

XieInitialize - initialize the XIE extension

Syntax

Status XieInitialize (display, extinfo_ret)
Display *display;
XieExtensionInfo **extinfo ret;

Arguments

display Specifies a connection to an X server.

extinfo_ret Returns the pointer to an XieExtensionInfo structure,

which contains information about the XIE server's

capabilities.

Returns

Zero on failure, nonzero on success.

Description

XieInitialize initializes the interface to the XIE extension and returns information about the XIE server's capabilities. XieInitialize should be called to establish version compatibility between client and server prior to making any other XIE request.

If successful, XieInitialize allocates and fills the XieExtensionInfo structure as follows:

The server_major_rev and server_minor_rev members are set to specify the highest version of the XIE protocol that the server supports. If the server version is higher than the XIElib version, the server will return the lower version, if it supports it.

The service_class member is set to the service-class supported by the XIE server. Service-class defines the recognized image-processing service sets supported by the X Image Extension standard; the two service classes currently defined are Full, the entire XIE protocol, and DIS, the Document Image Subset, a proper subset of Full XIE. The service_class member can be set to one of the standard values:

xieValFull xieValDIS

The alignment member is set to the pixel and scanline alignment for image data supported by the server. Values for this member can be either xieValAlignable or xieValArbitrary. xieValAlignable data units must fit evenly within a byte, or they must fill a byte, or fill a multiple of bytes; xieValArbitrary data units may fall at any bit address.

The uncnst_mantissa member is set to the number of bits in the server's floating-point format (including the sign bit). If the server uses fixed point, uncnst mantissa is set to zero.

The uncnst_min_exp member is set to the smallest (most negative) value n such that 2n is representable in the server's unconstrained data format.

The uncnst_max_exp member is set to the largest value n such that 2n - 1 is representable in the server's unconstrained data format.

The n_cnst_levels member is the number of items in the list cnst_levels. The items in the list cnst_levels are set to the levels that are "recommended" for constrained data by the server. A value of zero means 232 levels. The first event member is set to the value from which subsequent XIE events

The first_error member is set to the value from which subsequent XIE error values are based.

The memory allocated to *extinfo_ret* is freed when *display* is closed via XCloseDisplay; the client should <u>not</u> free this memory.

If not successful, XieInitialize sets **extinfo ret to NULL.

Structures

values are based.

```
typedef struct {
   unsigned server major rev;
   unsigned server minor rev;
   XieServiceClass service class;
   XieAlignment alignment:
   int uncnst mantissa;
   int uncnst min exp;
   int uncust max exp:
   int n cnst levels;
   unsigned long *cnst levels;
   int major opcode;
   int first event;
   int first error;
} XieExtensionInfo;
/* Definitions of Extension Name and Version Number */
#define xieMajorVersion
#define xieMinorVersion
                                              0
#define xieEarliestMinorVersion
                                              0
#define xieLatestMinorVersion
                                              0
/* Definitions of ServiceClass */
#define xieValFull
                                              1
#define xieValDIS
                                              2
/* Definitions of Alignment */
#define xieValAlignable
                                              1
#define xieValArbitrary
                                              2
```

XIElib - Startup Functions

XieQueryTechniques

Name

XieQueryTechniques - return information about the standard and private techniques that are supported by the server

Syntax

Status XieQueryTechniques (display, technique_group, ntechniques_ret, techniques_ret)

Display *display;

XieTechniqueGroup technique group;

int*ntechniques ret;

XieTechnique **techniques_ret;

Arguments

display Specifies a connection to an X server.

technique group Specifies the group of techniques for which the server is

to return information.

ntechniques ret Returns the number of items in the list of XieTechnique

structures.

techniques ret Returns the pointer to the list of XieTechnique

structures, which contains the information about the

selected group of techniques.

Returns

Zero on failure, nonzero on success.

Description

If successful, XieQueryTechniques allocates and fills each XieTechnique structure in the list as follows:

The member needs_param is set to True if the technique requires additional parameters; needs_param is set to False if the technique takes no parameters, or it has parameters that are optional. If parameters are optional, they must be totally omitted, or they must all be supplied. The member group is set to the group the technique belongs to. The member number is set to the numeric identifier assigned to the technique.

The member speed is set to the server's assessment of the speed of this technique relative to other techniques in the same group, where 0 is slowest and 255 is fastest.

The member name is set to the XIE compliant technique name string.

To free the memory allocated to techniques ret, use XieFreeTechniques.

On failure, ntechniques ret is set to zero and *techniques ret is set to NULL.

The standard technique group names that can be queried using XieQueryTechniques are:

Technique group	Meaning
xieValDefault	Select all default techniques

xieValAll	Select all supported techniques
xieValColorAlloc	Select color allocation techniques
xieValConstrain	Select techniques for constraining data
xieValConvertFromRGB	Select colorspace conversion techniques (for conversion from the RGB colorspace)
xieValConvertToRGB	Select colorspace conversion techniques (for conversion to the RGB colorspace)
xieValConvolve	Select techniques for handling convolution edge conditions
xieValDecode	Select image decoding (decompression) techniques
xieValDither	Select dithering techniques
xieValEncode	Select image encoding (compression) techniques
xieValGamut	Select colorspace conversion gamut compression techniques
xieValGeometry	Select geometric sampling techniques
xieValHistogram	Select match-histogram shapes
xieValWhiteAdjust	Select colorspace conversion white point adjustment techniques

If a vendor defined an additional private technique group, it could be discovered by querying for all groups.

Structures

```
typedef unsigned XieTechniqueGroup;
typedef struct {
   Bool needs param;
   XieTechniqueGroup group;
   unsigned int number;
   unsigned int speed;
   char *name;
} XieTechnique;
/* Definitions for TechniqueGroups */
#define xieValDefault
                                            0
#define xieValAll
                                            1
                                            2
#define xieValColorAlloc
#define xieValConstrain
                                            4
#define xieValConvertFromRGB
                                            6
#define xieValConvertToRGB
                                            8
#define xieValConvolve
                                            10
#define xieValDecode
                                            12
#define xieValDither
                                            14
#define xieValEncode
                                            16
#define xieValGamut
                                            18
#define xieValGeometry
                                            20
                                            22
#define xieValHistogram
#define xieValWhiteAdjust
                                            24
```

Errors

BadAlloc

Insufficient resources

BadValue

 $Unknown \ technique_group$

See Also

XieFreeTechniques

XIElib - Color List Functions

XieCreateColorList

Name

XieCreateColorList - create a color list

Syntax

XieColorList XieCreateColorList (*display*)
Display **display*;

Arguments

display Specifies a connection to an X server.

Returns

The color list identifier.

Description

XieCreateColorList creates a color list resource and returns its color list ID.

The color list created is an unpopulated server resource that can be used to store the list of colors allocated by XieFloConvertToIndex. The Colormap allocations that are recorded in a color list belong to the client that executed the photoflo that populated the resource (this is not necessarily the same client that created the color list). A color list cannot be the target of more than one active photoflo at a time. The contents of a color list may be queried using XieQueryColorList. All allocated cells can be explicitly purged from a color list using XiePurgeColorList. A color list can be destroyed using XieDestroyColorList.

Structures

typedef XID XieColorList;

Errors

BadAlloc Insufficient resources BadIdChoice Invalid color list

See Also

XieDestroyColorList, XiePurgeColorList, XieQueryColorList, XieFloConvertToIndex

XIElib - Color List Functions

${\bf Xie Destroy Color List}$

Name

XieDestroyColorList - destroy a color list

Syntax

void XieDestroyColorList (display, color_list)
 Display *display;
 XieColorList color list;

Arguments

display Specifies a connection to an X server. color_list Specifies the color list to be destroyed.

Description

XieDestroyColorList destroys the color list resource identified by *color_list*. Once destroyed, color list ID is no longer valid.

Structures

typedef XID XieColorList;

Errors

xieErrNoColorlist Invalid color list

See Also

XieCreateColorList

XIElib - Color List Functions

XiePurgeColorList

Name

XiePurgeColorList - purge all allocated cells from a color list

Syntax

void XiePurgeColorList (display, color_list)
 Display*display;
 XieColorList color_list;

Arguments

display Specifies a connection to an X server. color_list Specifies the color list to be purged.

Description

XiePurgeColorList frees the colors from the specified color list.

Structures

typedef XID XieColorList;

Errors

BadAccess Attempt to purge colors when color list is being written

by a photoflo

xieErrNoColorlist Invalid color list

See Also

XieCreateColorList, XieDestroyColorList, XieQueryColorList, XieFloConvertToIndex

XieQueryColorList

XIElib - Color List Functions

Name

XieQueryColorList - obtain a list of allocated Colormap indices

Syntax

Status XieQueryColorList (display, color_list, colormap_ret, ncolors_ret, colors_ret)

Display *display;

XieColorList color_list;

Colormap *colormap_ret;

unsigned *ncolors_ret;

unsigned long **colors ret;

Arguments

display Specifies a connection to an X server.

color_list Specifies the color list to query.

colormap ret Returns the Colormap from which the colors were

allocated.

ncolors_ret Returns the number of Colormap indices in the list. colors ret Returns the list of allocated Colormap indices.

Returns

Zero on failure, nonzero on success.

Description

XieQueryColorList allocates and returns a list of colors allocated by a ConvertToIndex element.

When there are no colors in color list, a zero status is returned, the value zero is returned for the colormap, and the list of colors is of length zero. The pointer to the list of allocated Colormap indices is set to NULL.

To free the memory allocated to colors ret, use XFree.

Structures

typedef XID XieColorList;

Errors

BadAlloc Insufficient resources xieErrNoColorlist Invalid color list

See Also

XieCreateColorList, XieDestroyColorList, XieQueryColorList, XieFloConvertToIndex

Name

XieCreateLUT - create a lookup table

Syntax

XieLut XieCreateLUT (display)
Display *display;

Arguments

display Specifies a connection to an X server.

Returns

The lookup table (LUT) identifier.

Description

XieCreateLUT creates a server resource that is used as a lookup table (LUT) by a Point element. A lookup table consists of one or three single-dimension arrays, each long enough to contain an entry for all possible pixels values in the image data to which the Point element will be applied.

The LUT is populated (or repopulated) with lookup table entries after the successful execution of a photoflo containing an ExportLUT element that targets lut. LUT data can be imported into a photoflo using an ImportLUT element.

Structures

typedef XID XieLut;

Errors

BadAlloc Insufficient resources

BadIDChoice Invalid LUT

See Also

XieDestroyLUT, XieFloImportLUT, XieFloExportLUT

Name

XieDestroyLUT - destroy a lookup table

Syntax

```
void XieDestroyLUT (display, lut)
Display *display;
XieLut lut;
```

Arguments

display Specifies a connection to an X server.

lut Specifies the ID of the LUT to be destroyed.

Description

XieDestroyLUT destroys the lookup table (LUT) identified by *lut*. Once destroyed, LUT ID is no longer valid.

Structures

typedef XID XieLut;

Errors

xieErrNoLut The value for the *lut* argument does not name a defined

LUT

See Also

XieDestroyLUT, XieFloImportLUT, XieFloExportLUT

XIElib - Photomap Functions

XieCreatePhotomap

Name

XieCreatePhotomap - create a photomap

Syntax

XiePhotomap XieCreatePhotomap (*display*) Display **display*;

Arguments

display Specifies a connection to an X server.

Returns

The photomap identifier.

Description

XieCreatePhotomap creates a photomap, a server resource that stores image data. Photomap data may be rendered for display or used as input to control or modify the rendition of another image.

Photomap attributes are defined when a photoflo containing an ExportPhotomap element populates the photomap with data.

Structures

typedef XID XiePhotomap;

Errors

BadAlloc Insufficient resources BadIdChoice Invalid photomap

See Also

XieDestroyPhotomap, XieQueryPhotomap, XieFloImportPhotomap, XieFloExportPhotomap

XIElib - Photomap Functions

XieDestroyPhotomap

Name

XieDestroyPhotomap - destroy a photomap

Syntax

void XieDestroyPhotomap (display, photomap)
 Display*display;
 XiePhotomap photomap;

Arguments

display Specifies a connection to an X server.

photomap Specifies the ID of the photomap to be destroyed.

Description

XieDestroyPhotomap destroys the photomap identified by *photomap*. Once destroyed, the photomap ID is no longer valid. A photomap is the XIE resource used to store image data in the server.

Structures

typedef XID XiePhotomap;

Errors

xieErrNoPhotomap The value for the *photomap* argument does not name a

defined photomap

See Also

 $\it XieCreatePhotomap$, $\it XieQueryPhotomap$, $\it XieFloImportPhotomap$, $\it XieFloExportPhotomap$

Name

XieQueryPhotomap - return the queriable attributes of a photomap

Syntax

```
Status XieQueryPhotomap (display, photomap, populated_ret, datatype_ret, class_ret, decode_technique_ret, width_ret, height_ret, levels_ret)
Display *display;
XiePhotomap photomap;
Bool *populated_ret;
XieDataType *datatype_ret;
XieDataClass *class_ret;
XieDecodeTechnique *decode_technique_ret;
XieLTriplet width_ret;
XieLTriplet height_ret;
XieLTriplet levels ret;
```

Arguments

displaySpecifies a connection to an X server.photomapSpecifies the photomap to be queried.populated_retReturns the status of the photomap.datatype_retReturns the type of data in the photomap.class retReturns the class of data in the photomap.

decode technique ret Returns the decode technique required to interpret the

data.

width_ret Returns the width, in pixels per band. height ret Returns the height, in pixels per band.

levels ret Returns the number of quantization levels per band.

Returns

Zero on failure, nonzero on success.

Description

A photomap is a server resource that stores image data. XieQueryPhotomap sets $populated_ret$ to indicate whether or not photomap has been populated with attributes and data. If $populated_ret$ is False, all remaining fields contain zeros.

datatype_ret reports whether the photomap contains constrained or unconstrained data, and is set to one of the following standard data type values:

xieValConstrained xieValUnconstrained

class_ret is the class of image data (that is, single-band or triple-band) and is set to one of the following standard data class values:

xieValSingleBand xieValTripleBand

width_ret and height_ret are set to the dimensions of the image data in pixels (per band). levels ret is set to the potential dynamic range, or number of

quantization levels (per band). If *datatype_ret* is set to unconstrained, the returned values for levels are zeros. If *class_ret* is xieValSingleBand, *width_ret*, *height_ret*, and *levels_ret* are only valid for element 0 in each of these vectors; elements 1 and 2 are unused and are returned as zeros.

decode_technique_ret is set to the decode technique that will be required to
interpret or decompress the data. Decode techniques define the techniques that
can be used to interpret uncompressed image data or decode compressed
images. decode_technique_ret can be set to one of the following standard decode
technique values:

```
xieValDecodeUncompressedSingle
xieValDecodeUncompressedTriple
xieValDecodeG31D
xieValDecodeG32D
xieValDecodeG42D
xieValDecodeJPEGBaseline
xieValDecodeJPEGLossless
xieValDecodeTIFF2
xieValDecodeTIFF2
```

If a vendor defined additional private decode techniques, $decode_technique_ret$ can be set to the values given to these techniques.

Structures

```
typedef unsigned XieDataClass;
typedef unsigned XieDataType;
typedef unsigned XieDecodeTechnique;
typedef unsigned long XieLTriplet[3];
typedef XID XiePhotomap:
/* Definitions of DataType */
#define xieValConstrained
                                            1
#define xieValUnconstrained
                                            2
/* Definitions of DataClass */
#define xieValSingleBand
                                            1
#define xieValTripleBand
                                            2
/* Definitions for DecodeTechniques */
#define xieValDecodeUncompressedSingle
                                            2
                                            3
#define xieValDecodeUncompressedTriple
#define xieValDecodeG31D
                                            4
#define xieValDecodeG32D
                                            6
#define xieValDecodeG42D
                                            8
#define xieValDecodeJPEGBaseline
                                            10
#define xieValDecodeJPEGLossless
                                            12
#define xieValDecodeTIFF2
                                            14
#define xieValDecodeTIFFPackBits
                                            16
```

Errors

xieErrNoPhotomap The value for the *photomap* argument does not name a

defined photomap.

xieErrNoFloAlloc Insufficient resources (for exmple, memory)

XieCreateROI

XIElib - ROI Functions

Name

XieCreateROI - create a Rectangles-Of-Interest

Syntax

XieRoi XieCreateROI (display) Display *display;

Arguments

display Specifies a connection to an X server.

Returns

The ROI (Rectangles-Of-Interest) identifier.

Description

XieCreateROI creates a server ROI (Rectangles-Of-Interest) resource, and returns its resource ID to the client.

Structures

typedef XID XieRoi;

Errors

BadAlloc Insufficient resources

BadIDChoice Invalid ROI

See Also

XieDestroyROI, XieFloImportROI, XieFloExportROI

XieDestroyROI

XIElib - ROI Functions

Name

XieDestroyROI - destroy a Rectangles-Of-Interest

Syntax

```
void XieDestroyROI (display, roi)
Display *display;
XieRoi roi;
```

Arguments

display Specifies a connection to an X server.
roi Specifies the ID of the ROI to be destroyed.

Description

XieDestroyROI destroys the Rectangles-Of-Interest (ROI) identified by *roi*. Once destroyed, *roi* is no longer valid.

Structures

typedef XID XieRoi;

Errors

xieErrNoROI The value for the *roi* argument does not name a defined

ROI

See Also

XieCreateROI

XIElib - Immediate Photoflo Functions XieCreatePhotospace

Name

XieCreatePhotospace - create a photospace

Syntax

XiePhotospace XieCreatePhotospace (display) Display *display;

Arguments

display Specifies a connection to an X server.

Returns

The photospace identifier.

Description

XieCreatePhotospace returns a resource-id for a new photospace that can be used to accommodate immediate photoflos instantiated by a client. Any client that needs to instantiate immediate photoflos must create at least one photospace.

Structures

typedef XID XiePhotospace;

Errors

BadAlloc Insufficient resources
BadIDChoice Invalid photospace

See Also

XieDestroyPhotospace, XieExecuteImmediate

XIElib - Immediate Photoflo Functions XieDestroyPhotospace

Name

XieDestroyPhotospace - destroy a photospace

Syntax

void XieDestroyPhotospace (display, photospace)
 Display *display;
 XiePhotospace photospace;

Arguments

display Specifies a connection to an X server.

photospace Specifies the ID of the photospace to be destroyed.

Description

XieDestroyPhotospace destroys a photospace. Prior to destroying the photospace, all photoflos that are currently active in the photospace will be aborted, exported data pending client retrieval will be freed, and the photoflos will be destroyed.

Structures

typedef XID XiePhotospace;

Errors

xieErrNoPhotospace The value for the *photospace* argument does not name

a defined photospace

See Also

XieCreatePhotospace

XIElib - Immediate Photoflo Functions XieExecuteImmediate

Name

XieExecuteImmediate - define and begin execution of an immediate photoflo

Syntax

Arguments

display Specifies a connection to an X server.

photospace Specifies the ID of the photospace to be executed. flo_id Specifies a particular instance of the photoflo to be

executed.

notify Specifies whether a PhotofloDone event must be sent

upon completion.

elem list Specifies the import, process, and export elements to be

executed.

elem count Specifies the number of items in elem list.

Description

XieExecuteImmediate begins the asynchronous execution of an *immediate* photoflo. The server does not save a copy of an immediate photoflo after the photoflo has completed execution and all data exported for the client have been retrieved. An immediate photoflo may therefore not be modified or totally redefined prior to subsequent executions. It is legal to have multiple unique instances of immediate photoflos (and stored photoflos) active concurrently.

The <code>photospace/flo_id</code> argument pair specifies the <code>instance</code> by which this photoflo will be identified in other requests, events, or errors. <code>notify</code> specifies whether a PhotofloDone event must be sent upon completion. The PhotofloDone event notifies the client that a photoflo has left the active state: it is no longer executing. <code>elem_list</code> defines the import, process, and export elements to be executed.

If any clients have blocked themselves during the execution of the photoflo (see XieAwait), they will become unblocked when the photoflo's state changes from active to nonexistent.

Care should be taken that the argument pair <code>elem_list/elem_count</code> matches a returned value (an array of XiePhotoElement structures) and argument <code>count</code> from a call to XieAllocatePhotofloGraph.

Structures

```
typedef XID XiePhotospace;

typedef struct {
   int elemType;
   /* union of ALL element types */
   union {
     ...
   }
   data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloElement Invalid element type(s) in *elem list*

xieErrNoFloID Invalid photospace/flo id argument pair has been

specified

xieErrNoFlo An error has been detected while defining, executing, or

accessing a photoflo (See Photoflo Errors).

See Also

XieAwait, XieAllocatePhotofloGraph

XIElib - Photoflo Functions

XieAllocatePhotofloGraph

Name

XieAllocatePhotofloGraph - allocate an array of XiePhotoElement structures

Syntax

XiePhotoElement *XieAllocatePhotofloGraph (count);
 unsigned int count;

Arguments

count

Specifies the number of XiePhotoElement structures to allocate.

Returns

The array of XiePhotoElement structures.

Description

XieAllocatePhotofloGraph allocates and returns a pointer to an array of XiePhotoElement structures; each field of each structure in the array is set to zero (0).

To free the memory allocated to the list of XiePhotoElement structures, use XieFreePhotofloGraph .

If XieAllocatePhotofloGraph is unable to create an XiePhotoElement array , it returns NULL.

Structures

```
typedef struct {
    int elemType;
    /* union of ALL element types */
    union {
        ...
        ...
    } data;
} XiePhotoElement;
```

See Also

XieFreePhotofloGraph, XieCreatePhotoflo, XieModifyPhotoflo, XieRedefinePhotoflo, XieExecutePhotoflo, XieExecuteImmediate

Name

XieCreatePhotoflo - create a stored photoflo

Syntax

```
XiePhotoflo XieCreatePhotoflo (display, elem_list, elem_count)
    Display *display;
    XiePhotoElement *elem_list;
    int elem_count;
```

Arguments

display Specifies a connection to an X server.

elem_list Specifies the defining array of XiePhotoElement

structures.

elem count Specifies the number of XiePhotoElement structures in

the array.

Returns

The photoflo identifier.

Description

XieCreatePhotoflo creates a *stored* photoflo resource, defines its complete contents using the contents of *elem_list*, sets it in the inactive state, and returns its resource-id. Stored photoflos persist beyond execution and may be modified or totally redefined prior to subsequent executions.

The returned photoflo identifier is a new resource-id that, along with the execution domain used for the photoflo, identifies this photoflo in other requests, events, or errors. <code>elem_list</code> defines the import, process, and export elements to be stored for execution. Although resources and parameters are specified at creation, no action is taken to validate them at that time. XieCreatePhotoflo will only store the photoflo's definition: parameter validation is delayed until an execute request is received.

Structures

```
typedef XID XiePhotoflo;

typedef struct {
    int elemType;
    /* union of ALL element types */
    union {
        ...
    } data;
} XiePhotoElement;
```

Errors

BadAlloc Insufficient resources
BadIdChoice Invalid photoflo

xieErrNoFloAlloc Insufficient resources (for example, memory) for

elem list

xie ErrNo Flo ElementInvalid element type(s) in *elem list*

An error has been detected while defining, executing, or accessing a photoflo (see Photoflo Errors). xieErrNoFlo

See Also

 $\label{locatePhotofloGraph} Xie Allocate Photoflo Graph,\ Xie Free Photoflo Graph,\ Xie Modify Photoflo,\ Xie Redefine Photoflo,\ Xie Execute Photoflo,\ Xie Query Photoflo,\ Xie Destroy Photoflo Photoflo,\ Xie Destroy Photoflo,$

XIElib - Stored Photoflo Functions

XieDestroyPhotoflo

Name

XieDestroyPhotoflo - destroy a stored photoflo

Syntax

void XieDestroyPhotoflo (display, photoflo)
 Display*display;
 XiePhotoflo photoflo;

Arguments

display Specifies a connection to an X server. photoflo Specifies the photoflo to be destroyed.

Description

XieDestroyPhotoflo destroys a stored photoflo. If *photoflo* is active, that is, executing, it is aborted and all exported data that are pending client retrieval are freed prior to destroying *photoflo*.

Structures

typedef XID XiePhotoflo;

Errors

xieErrNoPhotoflo The value for the *photoflo* argument does not name a

defined photoflo

See Also

XieCreatePhotoflo

XIElib - Stored Photoflo Functions

XieExecutePhotoflo

Name

XieExecutePhotoflo - execute a stored photoflo

Syntax

void XieExecutePhotoflo (display, photoflo, notify)
 Display *display;
 XiePhotoflo photoflo;
 Bool notify;

Arguments

display Specifies a connection to an X server. photoflo Specifies the photoflo to be executed.

notify Specifies that a PhotofloDone event must be sent upon

completion.

Description

XieExecutePhotoflo changes a stored photoflo to the active state. Execution is asynchronous. The photoflo returns to the inactive state when execution completes and all data exported for the client have been retrieved. It is legal to have multiple stored photoflos (and immediate photoflos) active concurrently.

notify specifies that a PhotofloDone event must be sent upon completion. A PhotofloDone event notifies the client that a photoflo has left the active state (it is no longer executing).

Stored photoflos persist beyond execution and may be modified or totally redefined prior to subsequent executions.

Structures

typedef XID XiePhotoflo;

Errors

xieErrNoPhotoflo The value for the photoflo argument does not name a

defined photoflo

xieErrNoFloAccess Attempt to execute *photoflo* when it is already active

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFlo An error has been detected while defining, executing, or

accessing a photoflo (see Photoflo Errors).

See Also

XieCreatePhotoflo, XieModifyPhotoflo, XieRedefinePhotoflo, XieQueryPhotoflo, XieDestroyPhotoflo, XieAbort, XieAwait, XieGetClientData, XiePutClientData

Name

XieModifyPhotoflo - modify a stored photoflo

Syntax

```
void XieModifyPhotoflo (display, photoflo, start, elem_list, elem_count)
    Display *display;
    XiePhotoflo photoflo;
    int start;
    XiePhotoElement *elem_list;
    int elem_count;
```

Arguments

display Specifies a connection to an X server. photoflo Specifies the photoflo to be modified.

start Specifies the index where element replacement is to

begin.

elem list Specifies an array of elements that will replace existing

elements.

elem count Specifies the number of items in elem list.

Description

XieModifyPhotoflo allows element parameters of a stored photoflo to be modified. Stored photoflos persist beyond execution and may be modified prior to subsequent executions.

start is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a *start* value of one (1).

XieModifyPhotoflo only allows *parameter* modification. No topological changes are allowed: elements cannot be deleted, inserted, or appended.

Structures

```
typedef XID XiePhotoflo;

typedef struct {
    int elemType;
    /* union of ALL element types */
    union {
        ...
        ...
      } data;
} XiePhotoElement;
```

Errors

xieErrNoPhotoflo The value for the *photoflo* argument does not name a

defined photoflo

xieErrNoFloAccess Attempt to change *photoflo* when it is already active

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloElement

Invalid element type(s) in *elem_list or* attempt to append additional element(s) to *photoflo*

An invalid start has been specified or xieErrNoFloSource

attempt to change input connections of type

XiePhototag in *elem list*

xieErrNoFlo An error has been detected while defining, executing, or

accessing a photoflo (see Photoflo Errors).

See Also

XieAllocatePhotofloGraph, XieFreePhotofloGraph, XieCreatePhotoflo, XieRedefinePhotoflo, XieExecutePhotoflo, XieQueryPhotoflo, XieDestroyPhotoflo

XieRedefinePhotoflo

XIElib - Stored Photoflo Functions

Name

XieRedefinePhotoflo - redefine a stored photoflo

Syntax

```
void XieRedefinePhotoflo (display, photoflo, elem_list, elem_count)
    Display *display;
    XiePhotoflo photoflo;
    XiePhotoElement *elem_list;
    int elem_count;
```

Arguments

display Specifies a connection to an X server. photoflo Specifies the photoflo to be redefined.

elem list Specifies an array of elements that will replace all

existing elements.

elem count Specifies the number of items in elem list.

Description

XieRedefinePhotoflo allows all elements of a stored photoflo to be removed and replaced with a new list. Stored photoflos persist beyond execution and may be totally redefined prior to subsequent executions.

There are no restrictions on changing element types or the array's size.

Structures

```
typedef XID XiePhotoflo;

typedef struct {
    int elemType;
    /* union of ALL element types */
    union {
        ...
        ...
     } data;
} XiePhotoElement;
```

Errors

xieErrNoPhotoflo The value for the *photoflo* argument does not name a

defined photoflo

 ${\tt xieErrNoFloAccess} \qquad {\tt Attempt\ to\ change\ \it photoflo\ when\ it\ is\ already\ active}$

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFlo An error has been detected while defining, executing, or

accessing a photoflo (see Photoflo Errors).

See Also

 $\label{locatePhotofloGraph} Xie Allocate Photoflo Graph, Xie Create Photoflo, Xie Modify Photoflo, Xie Execute Photoflo, Xie Query Photoflo, Xie Destroy Photoflo Allocate Photoflo, Xie Destroy Photoflo, Yie Destroy Pho$

XieQueryPhotoflo

XIElib - Photoflo Functions

Name

XieQueryPhotoflo - return the current status of a photoflo

Syntax

```
XieQueryPhotoflo(display, name_space, flo_id, state_ret, data_expected_ret, nexpected_ret, data_available_ret, navailable_ret)

Display *display;
unsigned long name_space;
unsigned long flo_id;
XiePhotofloState *state_ret;
XiePhototag **data_expected_ret;
unsigned int *nexpected_ret;
XiePhototag **data_available_ret;
unsigned int *navailable_ret;
```

Arguments

display Specifies a connection to an X server.

name space Specifies the execution domain used for the photoflo to

query.

flo id Specifies a particular instance of the photoflo to query.

state_retReturns the state of the photoflo.data_expected_retReturns a list of ImportClient elements.nexpected_retReturns the length of data_expected_ret.

data_available_ret Returns the length of data_expected_ret.

Returns a list of ExportClient elements.

Returns the length of data available ret.

Returns

Zero on failure, nonzero on success.

Description

XieQueryPhotoflo will return the current status of a photoflo.

The <code>name_space/flo_id</code> argument pair specifies the <code>instance</code> that identifies the photoflo that is being queried. <code>state_ret</code> indicates the state of the photoflo, and if XieQueryPhotoflo is successful, will return one of the following standard photoflo state values:

xieValInactive xieValActive xieValNonexistent

data_expected_ret is a list of ImportClient elements that are expecting data via XiePutClientData. data_available_ret is a list of ExportClient elements from which data are available (via XieGetClientData). Either or both of these lists may be of length zero, indicated by the returned values of nexpected_ret and navailable_ret.

XieQueryPhotoflo allocates memory for the list of ImportClient elements and the list of ExportClient elements. To free the memory allocated to <code>data_expected_ret</code> and <code>data_available_ret</code>, use XFree.

Specifying an unknown or invalid instance will return a $state_ret$ of nonexistent and zero length $data_expected_ret$ and $data_available_ret$ lists.

Structures

typedef unsigned XiePhotofloState;

/* Definitions of PhotofloState */	
#define xieValInactive	1
#define xieValActive	2
#define xieValNonexistent	3

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

See Also

XiePutClientData

XIElib - Client Data Functions

Name

XiePutClientData - send a stream of data to an active photoflo

Syntax

void XiePutClientData (display, name_space, flo_id, element, final, band_number, data, nbytes)

Display *display;

unsigned long name space;

unsigned long flo_id;

XiePhototag element;

Bool *final*;

unsigned band_number; unsigned char*data;

unsigned *nbytes*;

Arguments

display Specifies a connection to an X server.

name space Specifies the execution domain used for the photoflo to

receive the data.

flo id Specifies a particular instance of the photoflo to receive

the data.

element Specifies the element to receive the data.

final Specifies if the data is the last segment of data to be

sent. If *True*, then *data* represents the last data to be sent by the client. *False* indicates that more data will be sent (during a subsequent call to XiePutClientData).

band number Specifies which band of data is being sent.

data Specifies a counted list of bytes that comprises the data

stream.

nbytes Specifies the count of bytes that comprises the data

stream.

Description

XiePutClientData sends a stream of data to an active photoflo. Since the complete data object may be larger than can fit in a single protocol request, XIE allows the stream to be segmented; the last segment is signaled with a *final* flag.

The organization and contents of the data stream must match the parameters given to the ImportClient element or the results are undefined. An arbitrary amount of image data can be sent per request, whereas for nonimage data one or more complete aggregates must be sent per request (for example, one or more LUT array entries). If too many data are sent (for example, too many rectangles, or too many scanlines), the unwanted data are discarded. It is an error, however, to send too few data prior to signaling *final*.

For stored photoflos, *name_space* is always ServerIDSpace (the value zero) and *flo id* is the photoflo's resource-id. For immediate photoflos *name space* is a

photospace resource-id and *flo_id* is 32-bit value that uniquely identifies the instance of the photoflo within *name space*.

Structures

typedef unsigned XiePhototag;

Errors

xieErrNoFloAccess Executable photospace/flo_id argument pair not active

xieErrNoFloAlloc Insufficient resources (for example, memory)
xieErrNoFloElement Invalid element type specified by *element*

xieErrNoFloID Invalid photospace/flo id argument pair has been

specified

xieErrNoFloValue Invalid band number or

for nonimage data, data contains a partial aggregate

See Also

XieGetClientData

XIElib - Client Data Functions

Name

XieGetClientData - retrieve data from an ExportClient element within an active photoflo

Syntax

Status XieGetClientData (display, name_space, flo_id, element, max_bytes, terminate, band_number, new_state_ret, data_ret, nbytes_ret)

Display *display.

Display *display;

unsigned long name_space;

unsigned long flo_id;

XiePhototag element;

unsigned *max_bytes*;

Bool terminate;

unsigned band number;

XieExportState *new state ret;

unsigned char **data_ret;

unsigned *nbytes ret;

Arguments

display Specifies a connection to an X server.

name space Specifies the execution domain used for the photoflo

from which to retrieve data.

flo id Specifies a particular instance of the photoflo from

which to retrieve data.

element Specifies the element from which to retrieve the data.

max bytes Specifies the maximum number of bytes that can be

sent to the client.

terminate Specifies whether more data are wanted after this

request.

band number Specifies which band of data is being retrieved.

new state ret Returns the status of the ExportClient element after this

request.

data_ret Returns a counted list of bytes that comprises the data

stream.

nbytes ret Returns the count of bytes that comprises the data

stream.

Returns

Zero on failure, nonzero on success.

Description

XieGetClientData returns data in a contiguous read-once byte stream, which can be requested in segments that are limited in size by the amount the client desires or the amount of data available from the server. The format of the data depends on the parameters given to the ExportClient element from which the data are requested.

new_state_ret returns the state of the ExportClient element after this request
and can be set to one of the following standard export state values:

xieValExportDonexieValExportMore xieValExportEmpty xieValExportError

> If the request is sent to an ExportClient element that either: does not have any data, was terminated by a previous XieGetClientData call, or has already returned all its data (ExportDone sent), the request will return a zero length data ret stream.

> Image data are always retrieved from the server as a byte stream, whereas nonimage data are always returned by the server as one or more complete aggregates. max_bytes is effectively rounded down by the server to the match the nearest aggregate size.

For stored photoflos, name space is always ServerIDSpace (the value zero) and flo id is the photoflo's resource-id. For immediate photoflos name space is a photospace resource-id and *flo id* is a 32-bit value that uniquely identifies the instance of the photoflo within name space.

To free the memory allocated to data ret, use XFree.

Structures

typedef unsigned XieExportState; typedef unsigned XiePhototag;

/* Definitions of ExportState */	
#define xieValExportDone	1
#define xieValExportMore	2
#define xieValExportEmpty	3
#define xieValExportError	4

Errors

xieErrNoFloAccess	Executable <i>photospace/flo id</i> argument pair not active
xieErrNoFloAlloc	Insufficient resources (for example, memory)
xieErrNoFloElement	Invalid element type specified by <i>element</i>
xieErrNoFloID	Invalid <i>photospace/flo id</i> argument pair has been
	specified

Invalid band number xieErrNoFloValue

See Also

XiePutClientData, XieQueryPhotoflo, XieExecutePhotoflo, XieFloExportClientHistogram, XieFloExportClientLUT, XieFloExportClientPhoto, XieFloExportClientROI

XieAbort

XIElib - Abort and Await Functions

Name

XieAbort - prematurely terminate execution of a photoflo

Syntax

```
void XieAbort (display, name_space, flo_id);
   Display *display;
   unsigned long name_space;
   unsigned long flo_id;
```

Arguments

display Specifies a connection to an X server.

name space Specifies the execution domain used for the photoflo to

abort.

flo id Specifies a particular instance of the photoflo to abort.

Description

XieAbort will prematurely terminate execution of the photoflo specified by $name_space$ and flo_id . Any output from the photoflo that is pending client retrieval is freed. Stored photoflos are returned to the inactive state; immediate photoflos are destroyed.

If the photoflo specified by *name_space* and *flo_id* is either invalid or not active, no action is taken; it is not an error, and nothing is destroyed.

For stored photoflos, <code>name_space</code> is always ServerIDSpace (the value zero) and <code>flo_id</code> is the photoflo's resource-id. For immediate photoflos <code>name_space</code> is a photospace resource-id and <code>flo_id</code> is 32-bit value that uniquely identifies the instance of the photoflo within <code>name_space</code>.

See Also

Xie Execute Photoflo, Xie Execute Immediate

Name

XieAwait - block all further requests for this client connection from being honored by the server while the photoflo is active

Syntax

```
void XieAwait (display, name_space, flo_id);
   Display *display;
   unsigned long name_space;
   unsigned long flo id;
```

Arguments

display Specifies a connection to an X server.

name_space Specifies the execution domain used for the photoflo to

block requests.

flo id Specifies a particular instance of the photoflo to block

requests.

Description

XieAwait blocks all further requests for this client connection from being honored by the server while the photoflo, specified by *name_space* and *flo_id*, is active. When the photoflo transitions from the active state, blocked requests are allowed to be processed in the order received.

If the photoflo specified by *name_space* and *flo_id* is either invalid or not active, no action is taken; it is not an error, and the client is not blocked.

For stored photoflos, $name_space$ is always ServerIDSpace (the value zero) and flo_id is the photoflo's resource-id. For immediate photoflos $name_space$ is a photospace resource-id and flo_id is 32-bit value that uniquely identifies the instance of the photoflo within $name_space$.

Warning

Calling XieAwait before sending all import data or before retrieving all export data will block the client from sending or retrieving the remaining data. This also will prevent completion of the photoflo and prevent any and all protocol requests from this client from being honored. This deadlock can be broken only by another client completing or aborting the photoflo (to release the Await), or by breaking the client connection.

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

See Also

 $\it Xie Execute Photo Flo, Xie Execute Immediate$

XIElib - Photoflo Element Functions XieFloImportClientLUT

Name

XieFloImportClientLUT - specify an ImportClientLUT element and set its parameters

Syntax

 $void\ XieFloImportClientLUT\ (element,\ data_class,\ band_order,\ length,\ levels)$

XiePhotoElement *element; XieDataClass data_class; XieOrientation band_order; XieLTriplet length; XieLevels levels;

Arguments

element Specifies the XiePhotoElement structure to use.

data_class Specifies the number of lookup arrays to expect.

band_order Specifies the order of triple band arrays. Specifies the number of entries per array.

levels Specifies the number of quantization levels represented

per array.

Description

An ImportClientLUT element accepts lookup table data from the protocol stream. The transport of data through the protocol stream is accomplished using XiePutClientData. This data is accepted by the Point, ExportLUT, and ExportClientLUT elements.

data_class, which specifies the number of lookup arrays to expect, can be set to one of the following standard data class values:

xieValSingleBand xieValTripleBand

The *length* of each array should match the number of source image levels that will be remapped through the array. When a triple band image is to be remapped through a single band array, the *length* of the array should match the product of the source image levels of all three bands; in this case, *band_order* specifies the order in which pixels from a triple band image should be combined to form indices for a single band array. *band_order* can be set to one of the following standard orientation values:

xieValLSFirst xieValMSFirst

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: for example, red is the least significant band of RGB data. When one LUT array is used with triple band data, the algorithm for computing combined array indices, based on *band order*, is:

LUT band order	LUT indexing algorithm for combining pixel values
LSFirst	<pre>index = value[0] + value[1] x levels[0] + value[2] x levels[0] x levels[1]</pre>
MSFirst	<pre>index = value[2] + value[1] x levels[2] + value[0] x levels[2] x levels[1]</pre>

When three LUT arrays are used, <code>band_order</code> specifies whether this band corresponds with the least significant or most significant LUT array. Each array is transported as a separate data stream. For example, if the colorspace of the image data is RGB:

band	LSFirst	MSFirst
0	Red array	Blue array
1	Green array	Green array
2	Blue array	Red array

Structures

XieFloImportClientLUT sets the XiePhotoElement structure field elemType to xieElemImportClientLUT, which identifies the element as an ImportClientLUT, and sets the fields of the member structure ImportClientLUT using the arguments in the argument list.

```
typedef unsigned XieDataClass;
typedef unsigned XieOrientation;
typedef unsigned long XieLTriplet[3];
typedef unsigned long XieLevels[3];
typedef struct {
   int elemType;
   union {
       struct {
          XieDataClass data class;
          XieOrientation band order;
          XieLTriplet length;
          XieLevels levels;
       } ImportClientLUT;
   } data:
} XiePhotoElement;
/* Definitions of DataClass */
#define xieValSingleBand
                                              1
#define xieValTripleBand
                                              2
/* Definitions of Orientation Types */
#define xieValLSFirst
                                              1
#define xieValMSFirst
                                              2
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

levels is incompatible with the server's depth-handling xie ErrNoFloMatch

capabilities
Invalid data_class or band_order xieErrNoFloValue

See Also

XiePutClientData, XieQueryPhotoflo, XieFloExportLUT, XieFloExportClientLUT, XieFloPoint, XieFloImportLUT

XIElib - Photoflo Element Functions XieFloImportClientPhoto

Name

XieFloImportClientPhoto - specify an ImportClientPhoto element and set its parameters

Syntax

void XieFloImportClientPhoto (element, data_class, width, height, levels, notify, decode tech, decode param)

XiePhotoElement *element; XieDataClass data_class; XieLTriplet width; XieLTriplet height; XieLevels levels;

XieDecodeTechnique decode tech;

XiePointer decode param;

Arguments

Bool *notify*;

element Specifies the XiePhotoElement structure to use.

data_classSpecifies whether the data is single band or triple band.widthSpecifies the width of the image in pixels per band.heightSpecifies the height of the image in pixels per band.levelsSpecifies the number of quantization levels per band.notifySpecifies whether to enable sending DecodeNotify

events.

decode tech Specifies the decode technique required to interpret the

image.

decode param Specifies the list of additional parameters required by

decode tech.

Description

An ImportClientPhoto element accepts image data from the protocol stream. This data may be processed for display or used as *process domain* data. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels. The attributes and organization of the expected data stream are fully specified by the parameters. The actual transport of image data through the protocol stream is requested using XiePutClientData.

notify enables DecodeNotify events to be sent if anomalies are encountered while interpreting the imported image data: either an error has been encountered while decoding an image or the image data received does not satisfy the expected dimensions.

Only constrained data can be sent through the protocol stream; therefore, *levels* must be valid.

data_class specifies whether the data is single band or triple band and can be set to one of the following standard data class values:

```
xieValSingleBand
xieValTripleBand
```

Decode techniques define the techniques that can be used to interpret uncompressed image data or decode compressed images. *decode_tech* can be assigned one of the following standard decode technique values:

```
xieValDecodeUncompressedSingle
xieValDecodeUncompressedTriple
xieValDecodeG31D
xieValDecodeG32D
xieValDecodeG42D
xieValDecodeJPEGBaseline
xieValDecodeJPEGLossless
xieValDecodeTIFF2
xieValDecodeTIFFPackBits
```

If a vendor defined additional private decode techniques, the values given to these techniques can be assigned to *decode tech*.

Output Attributes

Class class of imported image

Type constrained

Width width of imported image (in pixels)
Height height of imported image (in pixels)

Levels levels of imported image

Structures

XieFloImportClientPhoto sets the XiePhotoElement structure field elemType to xieElemImportClientPhoto, which identifies the element as an ImportClientPhoto, and sets the fields of the member structure ImportClientPhoto using the arguments in the argument list.

```
typedef unsigned XieDataClass;
typedef unsigned XieDecodeTechnique;
typedef unsigned long XieLTriplet[3];
typedef unsigned long XieLevels[3];
typedef struct {
   int elemType;
   union {
       struct {
          XieDataClass data class;
          XieLTriplet width;
          XieLTriplet height;
          XieLevels levels:
          Bool notify;
          XieDecodeTechnique decode tech;
          XiePointer decode param;
       } ImportClientPhoto;
```

} data: } XiePhotoElement; /* Definitions of DataClass */ #define xieValSingleBand 1 #define xieValTripleBand 2 /* Definitions for DecodeTechniques */ #define xieValDecodeUncompressedSingle 2 #define xieValDecodeUncompressedTriple 3 #define xieValDecodeG31D 4 #define xieValDecodeG32D 6 #define xieValDecodeG42D 8 #define xieValDecodeJPEGBaseline 10 #define xieValDecodeJPEGLossless 12 #define xieValDecodeTIFF2 14 #define xieValDecodeTIFFPackBits 16

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloMatch levels is incompatible with the server's depth-handling

capabilities

xieErrNoFloTechnique Invalid decode_tech or decode_param

xieErrNoFloValue Invalid width, height, levels (zero) or

invalid data class

See Also

XieTecDecodeUncompressedSingle, XieTecDecodeUncompressedTriple, XieTecDecodeG31D, XieTecDecodeG32D, XieTecDecodeG42D, XieTecDecodeTIFF2, XieTecDecodeTIFFPackBits, XieTecDecodeJPEGBaseline, XieTecDecodeJPEGLossless

XIElib - Photoflo Element Functions XieFloImportClientROI

Name

XieFloImportClientROI - specify an ImportClientROI element and set its parameters

Syntax

```
void XieFloImportClientROI (element, rectangles);
   XiePhotoElement *element;
   unsigned int rectangles;
```

Arguments

element Specifies the XiePhotoElement structure to use. rectangles Specifies the number of rectangles expected.

Description

An ImportClientROI element accepts a list of rectangles from the protocol stream. These data can be used as input to a *process domain* or an ExportROI or ExportClientROI element. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels. The actual transport of data through the protocol stream is accomplished using XiePutClientData (the *band_number* parameter of XiePutClientData is ignored).

Structures

XieFloImportClientROI sets the XiePhotoElement structure field elemType to xieElemImportClientROI, which identifies the element as an ImportClientROI, and sets the fields of the member structure ImportClientROI using the arguments in the argument list.

```
typedef struct {
    int elemType;
    union {
        ...
        struct {
            unsigned int rectangles;
        } ImportClientROI;
        ...
    } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

See Also

XIElib - Photoflo Element Functions XieFloImportDrawable

Name

XieFloImportDrawable - specify an ImportDrawable element and set its parameters

Syntax

Arguments

Specifies the XiePhotoElement structure to use. element Specifies the Drawable resource supplying the data. drawable Specifies the left corner of the region of the data to be src x imported. Specifies the upper corner of the region of the data to src_y be imported. Specifies the width of the region of the data to be width imported. height Specifies the height of the region of the data to be imported. fill Specifies the Colormap index to use for all regions that are obscured.

Specifies whether to enable sending ImportObscured

events.

Description

notify

An ImportDrawable element allows access to data existing in a Drawable. This data may be processed for display or, if *drawable* is one bit deep, used as *process domain* data. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels.

notify enables ImportObscured events to be sent if data for one or more regions of a Window are obscured and cannot be retrieved from backing store. The arguments src_x , src_y , width, and height specify the region of data to be imported from drawable, where src_x and src_y define the upper-left corner of the region.

Output Attributes

Class single band

```
Type constrained
Width width
Height height
Levels 2depth (that is, drawable depth)
```

Structures

XieFloImportDrawable sets the XiePhotoElement structure field elemType to xieElemImportDrawable, which identifies the element as an ImportDrawable, and sets the fields of the member structure ImportDrawable using the arguments in the argument list.

```
typedef struct {
    int elemType;
    union {
        ...
        struct {
            Drawable drawable;
            int src_x;
            int src_y;
            unsigned int width;
            unsigned int height;
            unsigned long fill;
            Bool notify;
        } ImportDrawable;
        ...
    } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloDrawableInvalid drawablexieErrNoFloValueInvalid region width, height, src x, src y

Functions

XieFloImportDrawablePlane

Name

XieFloImportDrawablePlane - specify an ImportDrawablePlane element and set its parameters

Syntax

Arguments

element	Specifies the XiePhotoElement structure to use.
drawable	Specifies the Drawable resource supplying the data.
src_x	Specifies the left corner of the region of the data to be imported.
src_y	Specifies the upper corner of the region of the data to
	be imported.
width	Specifies the width of the region of the data to be
	imported.
height	Specifies the height of the region of the data to be
	imported.
fill	Specifies the Colormap index to use for all regions that

are obscured.

 $\begin{array}{ll} \textit{bit_plane} & \text{Specifies the plane to be imported from } \textit{drawable}. \\ \textit{notify} & \text{Specifies whether to enable sending ImportObscured} \end{array}$

events.

Description

An ImportDrawablePlane event allows access to a single plane of data existing in a Drawable. This data may be processed for display or used as *process domain* data. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels.

notify enables ImportObscured events to be sent if data for one or more regions of a Window are obscured and cannot be retrieved from backing store. The arguments src_x , src_y , width, and height specify the region of data to be imported from drawable, where src_x and src_y define the upper-left corner of the region.

 bit_plane must have exactly one bit set to one (1), and the value of bit_plane must be less than or equal to , where n is the depth of drawable. This single bit selects the corresponding bit to be extracted from pixels within drawable.

Output Attributes

Class single band
Type constrained
Width width
Height height
Levels 2

Structures

XieFloImportDrawablePlane sets the XiePhotoElement structure field elemType to xieElemImportDrawablePlane, which identifies the element as an ImportDrawablePlane, and sets the fields of the member structure ImportDrawablePlane using the arguments in the argument list.

```
typedef struct {
    int elemType;
    union {
        ...
        struct {
            Drawable drawable;
            int src_x;
            int src_y;
            unsigned int width;
            unsigned int height;
            unsigned long fill;
            unsigned long bit_plane;
            Bool notify;
        } ImportDrawablePlane;
        ...
    } data;
} XiePhotoElement;
```

Errors

 ${\it xie ErrNo Flo Drawable} \quad {\it Invalid} \ {\it drawable}$

xieErrNoFloValue Invalid bit plane or region width, height, src x, src y

Name

XieFloImportLUT - specify an ImportLUT element and set its parameters

Syntax

```
void XieFloImportLUT (element, lut)
    XiePhotoElement *element;
    XieLut lut;
```

Arguments

element Specifies the XiePhotoElement structure to use.lut Specifies the LUT resource supplying the lookup table.

Description

An ImportLUT element allows access to lookup table data existing in a LUT resource. These data are accepted by the Point, ExportLUT, and ExportClientLUT elements.

Attributes of the lookup table data are inherited from *lut*.

Structures

XieFloImportLUT sets the XiePhotoElement structure field elemType to xieElemImportLUT, which identifies the element as an ImportLUT, and sets the fields of the member structure ImportLUT using the arguments in the argument list.

```
typedef XID XieLut;
typedef struct {
   int elemType;
   union {
     ...
     struct {
         XieLut lut;
     } ImportLUT;
     ...
   } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAccess xieErrNoFloAlloc xieErrNoFloLUT Attempt to import from lut before it has been populated Insufficient resources (for example, memory) An unknown lut has been specified

XIElib - Photoflo Element Functions XieFloImportPhotomap

Name

XieFloImportPhotomap - specify an ImportPhotomap element and set its parameters

Syntax

void XieFloImportPhotomap (element, photomap, notify)
 XiePhotoElement *element;
 XiePhotomap photomap;
 Bool notify;

Arguments

elementSpecifies the XiePhotoElement structure to use.photomapSpecifies the photomap resource supplying image data.notifySpecifies whether to enable sending DecodeNotify

events.

Description

An ImportPhotomap element allows access to image data existing in a photomap; a photomap is a server resource that can be used to store image data. This data may be processed for display or used as process domain data (if its levels attribute is 2), or it may be used as source to ExportPhotomap or ExportClientPhoto or any other element which takes image data as input. A process domain is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels.

notify enables DecodeNotify events to be sent if anomalies are encountered while decoding compressed data: either an error has been encountered while decoding an image or the image data received does not satisfy the expected dimensions.

Attributes of the source data are inherited from *photomap*.

Output Attributes

Class same as photomap
Type same as photomap
Width same as photomap
Height same as photomap
Levels same as photomap

Structures

XieFloImportPhotomap sets the XiePhotoElement structure field elemType to xieElemImportPhotomap, which identifies the element as an ImportPhotomap, and sets the fields of the member structure ImportPhotomap using the arguments in the argument list.

typedef XID XiePhotomap;

```
typedef struct {
   int elemType;
   union {
     ...
     struct {
          XiePhotomap photomap;
          Bool notify;
     } ImportPhotomap;
     ...
   } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAccess Attempt to import from *photomap* before it has been

populated

xieErrNoFloAlloc Insufficient resources (for example, memory) xieErrNoFloPhotomap An unknown *photomap* has been specified

See Also

XieFloExportPhotomap, XIeFloExportClientPhoto

Name

XieFloImportROI - specify an ImportROI element and set its parameters

Syntax

```
void XieFloImportROI (element, roi)
XiePhotoElement *element;
XieRoi roi;
```

Arguments

element roi Specifies the XiePhotoElement structure to use. Specifies the ID of the ROI supplying the list-of-rectangles.

Description

An ImportROI element allows access to a list-of-rectangles existing in a ROI resource. This data may be referenced by a *process domain*, or used as input to an ExportClientROI or ExportROI element. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels.

Structures

XieFloImportROI sets the XiePhotoElement structure field elemType to xieElemImportROI, which identifies the element as an ImportROI, and sets the fields of the member structure ImportROI using the arguments in the argument list

```
typedef XID XieRoi;
typedef struct {
    int elemType;
    union {
        ...
        struct {
            XieRoi roi;
        } ImportROI;
        ...
    } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAccess xieErrNoFloAlloc xieErrNoFloPhotomap Attempt to import from *roi* before it has been populated Insufficient resources (for example, memory)

An unknown roi has been specified

See Also

XieFloExportROI, XieFloExportClientROI

XieFloArithmetic

XIElib - Photoflo Element Functions

Name

XieFloArithmetic - specify an Arithmetic element and set its parameters

Syntax

void XieFloArithmetic (element, src1, src2, domain, constant, operator, band mask)

XiePhotoElement *element;

XiePhototag *src1*; XiePhototag *src2*;

XieProcessDomain *domain;

XieConstant constant;

XieArithmeticOp *operator*; unsigned int *band mask*;

Arguments

element Specifies the XiePhotoElement structure to use.src1 Specifies the phototag of the first data source.

src2 Specifies the phototag of the second data source, or 0 if

none.

domain Specifies the subset of source data that will be operated

on.

constant Specifies the constant data source (if src2 is 0).
operator Specifies the arithmetic operation to be performed.

band_mask Specifies which bands are to be operated on.

Description

An Arithmetic element produces output data by performing an addition, subtraction, minimum, or maximum operation between two data sources or between a single data source and a constant. Furthermore, multiplication, division, or gamma correction may by applied to a single data source.

When two sources are involved, src1 and src2 are the phototags of the elements supplying source data (constant is ignored). A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). If the operation is to involve a constant, src1 is one operand, src2 must be zero, and constant is used as the other operand.

When two sources are involved, all attributes, other than *width* and *height*, must match; all output attributes are inherited from *src*1.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by domain must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be

provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

Only bands selected by <code>band_mask</code> are subject to processing. Other bands present in the image are passed through to the output. For example, a <code>band_mask</code> of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a <code>band_mask</code> of 1112. Using <code>band_mask</code> to select source data that have two (2) or less <code>levels</code> is not permitted.

Pixel computations that would lead to errors, will yield valid server-dependent values (for example, dividing by a constrained pixel value of zero might result in a value of *levels-1*).

The valid operations for the Arithmetic process element are:

Operator	src1 (operator) src2	src1 (operator) constant
xieValAdd	src1 + src2	src1 + constant
xieValSub	src1 - src2	src1 - constant
xieValSubRev	src2 - src1	constant - src1
xieValMul		src1 * constant
xieValDiv		src1 / constant
xieValDivRev		constant / src1
xieValMin	minimum(src1, src2)	minimum(src1, constant)
xieValMax	maximum(src1, src2)	maximum(src1, constant)
xieValGamma (constrained)		(levels - 1) * ((src1 / (levels - 1))constant)
xieValGamma (unconstraine d)		Src1constant

Output Attributes

Class	same as src1
Type	same as src1
Width	same as src1
Height	same as src1
Levels	same as src1

Structures

XieFloArithmetic sets the XiePhotoElement structure field elemType to xieElemArithmetic, which identifies the element as an Arithmetic, and sets the fields of the member structure Arithmetic using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef unsigned XieArithmeticOp;
typedef struct {
    int offset_x;
    int offset_y;
```

```
XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src1;
          XiePhototag src2;
          XieProcessDomain domain;
          XieConstant constant;
          XieArithmeticOp operator;
          unsigned int band mask;
       } Arithmetic:
   } data;
} XiePhotoElement;
/* Definitions of ArithmeticOperations */
#define xieValAdd
                                             1
#define xieValSub
                                             3
#define xieValSubRev
                                             4
#define xieValMul
                                             5
#define xieValDiv
#define xieValDivRev
                                            6
                                            7
#define xieValMin
                                            8
#define xieValMax
#define xieValGamma
                                            9
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloDomainInvalid domainxieErrNoFloMatchClass, type, or levels differ between src1 and src2 or
selected data source are bitonalxieErrNoFloOperatorInvalid operatorxieErrNoFloSourceInvalid src1 or src2 or
src2 has been specified with a monadic operator

XIElib - Photoflo Element Functions

XieFloBandCombine

Name

XieFloBandCombine - specify a BandCombine element and set its parameters

Syntax

```
void XieFloBandCombine (element, src1, src2, src3)
    XiePhotoElement *element;
    XiePhototag src1;
    XiePhototag src2;
    XiePhototag src3;
```

Arguments

element	Specifies the XiePhotoElement structure to use.
src1	Specifies the first element supplying source data.
src2	Specifies the second element supplying source data.
src3	Specifies the third element supplying source data.

Description

A BandCombine element merges three single band data sources to produce a triple band result. The arguments src1, src2, and src3 must be of the same type, and each source must be single band. Other attributes that are taken from the individual sources may differ. The output will be triple band.

Output Attributes

Class	triple band
Type	same as <i>src1</i>
Width	same as <i>src</i> s
Height	same as <i>src</i> s
Levels	same as <i>src</i> s

Structures

XieFloBandCombine sets the XiePhotoElement structure field elemType to xieElemBandCombine, which identifies the element as a BandCombine, and sets the fields of the member structure BandCombine using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef struct {
   int elemType;
   union {
     ...
     struct {
        XiePhototag src1;
        XiePhototag src2;
        XiePhototag src3;
        XiePhototag src3;
}
```

```
} BandCombine;
...
} data;
} XiePhotoElement;
```

Errors

Insufficient resources (for example, memory) A source has more than one band orxie ErrNo Flo Alloc

xieErrNoFloMatch

type differs between sources

Invalid *src1*, *src2*, or *src3* xieErrNoFloSource

XIElib - Photoflo Element Functions

XieFloBandExtract

Name

XieFloBandExtract - specify a BandExtract element and set its parameters

Syntax

void XieFloBandExtract (element, src, levels, bias, coefficients)
 XiePhotoElement *element;
 XiePhototag src;
 unsigned int levels;
 double bias;
 XieConstant coefficients;

Arguments

element Specifies the XiePhotoElement structure to use.
 src Specifies the element supplying source data.
 levels Specifies the number of quantization levels for the

output.

bias Specifies the value to be added to each output pixel. coefficients Specifies the proportion of each band in src to pixelsin

the single band result.

Description

A BandExtract element produces single band output data from a triple band source by multiplying a pixel value from each source band by its corresponding *coefficient* and then summing the results with the *bias* value.

coefficients is a three-element array that determines the proportion of each source band pixel that is used to form the output. *levels* is used as the levels attribute of the output data if the *src* data are constrained; otherwise, it is ignored.

The source data must be triple band, and all bands must have equal dimensions. The output data will be single band, with levels taken from the *levels* parameter, if the data type is constrained. All other attributes are inherited from src.

Output Attributes

 $\begin{array}{ll} \text{Class} & \text{single band} \\ \text{Type} & \text{same as } src \\ \text{Width} & \text{same as } src \\ \text{Height} & \text{same as } src \end{array}$

Levels levels if src is contrained, else unknown

Structures

 fields of the member structure $\mbox{\sc BandExtract}$ using the arguments in the argument list.

```
typedef float XieConstant[3];
typedef unsigned XiePhototag;

typedef struct {
    int elemType;
    union {
        ...
        struct {
            XiePhototag src;
            unsigned int levels;
            float bias;
            XieConstant coefficients;
        } BandExtract;
        ...
    } data;
} XiePhotoElement;

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)
```

src is not triple band or

Invaİid *src*

unequal interband dimensions

xieErrNoFloMatch

xieErrNoFloSource

Name

XieFloBandSelect - specify a BandSelect element and set its parameters

Syntax

```
void XieFloBandSelect (element, src, band_number)
    XiePhotoElement *element;
    XiePhototag src;
    unsigned int band number;
```

Arguments

elementsrcSpecifies the XiePhotoElement structure to use.Specifies the element supplying source data.

band number Specifies which src band is to be selected to provide the

output data.

Description

A BandSelect element produces single band output data by selecting a single band from a triple band source.

Output Attributes

 $\begin{array}{cc} \text{Class} & \text{single band} \\ \text{Type} & \text{same as } src \end{array}$

Width same as band selected from src
Height same as band selected from src
Levels same as band selected from src

Structures

XieFloBandSelect sets the XiePhotoElement structure field elemType to xieElemBandSelect, which identifies the element as a BandSelect, and sets the fields of the member structure BandSelect using the arguments in the argument list.

typedef unsigned XiePhototag;

```
typedef struct {
   int elemType;
   union {
     ...
     struct {
         XiePhototag src;
         unsigned int band_number;
     } BandSelect;
     ...
   } data;
} XiePhotoElement;
```

Errors

 $\begin{array}{ll} \text{xieErrNoFloAlloc} & \text{Insufficient resources (for example, memory)} \\ \text{xieErrNoFloMatch} & src \text{ is not triple band} \\ \text{xieErrNoFloSource} & \text{Invalid } src \\ \text{xieErrNoFloValue} & \text{Invalid } band_number \end{array}$

Name

XieFloBlend - specify a Blend element and set its parameters

Syntax

void XieFloBlend (element, src1, src2, src_constant, alpha, alpha_const, domain, band_mask)

XiePhotoElement *element;

XiePhototag *src1*; XiePhototag *src2*;

XieConstant src constant;

XiePhototag *alpha*; double *alpha* const;

XieProcessDomain*domain; unsigned int band mask:

Arguments

element Specifies the XiePhotoElement structure to use.src1 Specifies the phototag of the first data source.

src2 Specifies the phototag of the second data source, else 0.

src_constant Specifies a constant data source, if src2 is 0.

alpha Specifies the blend proportion for each processed pixel.

alpha_const Specifies the constant blend proportion for each

processed pixel.

domain Specifies the subset of source data that will be operated

on.

band mask Specifies which bands are to be operated on.

Description

A Blend element produces output data from two data sources or a single data source and a constant. Each output pixel is a percentage combination of the source values, as controlled by an alpha input image or an alpha constant.

When two sources are involved, src1 and src2 are the phototags of the elements supplying source data; $src_constant$ is ignored. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). If the operation is to involve a constant, src1 is one operand, src2 must be zero, and $src_constant$ is used as the other operand. If alpha is nonzero, it controls the blend proportion for each pixel that is processed, otherwise $alpha_const$ provides this control. processed may control the subset of source data that will be operated on. Only bands selected by the processed are subject to processing. Other bands present in the image are passed through to the output. For example, a processed of processed of processed indicates that only the "least significant band" would be processed; operating on all bands requires a processed of processed is not permitted.

When two sources are involved, all attributes, other that *width* and *height*, must match. If *alpha* is nonzero, it must be a source of constrained data.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by domain must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

Within the intersection of the source(s) and *domain*, each output pixel is a blend of the corresponding pixels from src1 and src2 (or src1 pixels blended with $src_constant$). The degree of blend is determined by the corresponding pixel taken from alpha or the value of $alpha_const$. If alpha is nonzero, the proportion of blend is further scaled by $alpha_const$:

```
\begin{aligned} & \text{output} = src1*(1 - alpha / alpha\_const) + src2*(alpha / alpha\_const) \\ & \text{(where } alpha\_const \text{ is greater than } 0.0) \end{aligned} if alpha is zero: & \text{output} = src1*(1 - alpha\_const) + src2*alpha\_const \\ & \text{(where } alpha\_const \text{ is in the range } [0.0, 1.0]) \end{aligned}
```

Output Attributes

Class	same as <i>src1</i>
Type	same as src1
Width	same as src1
Height	same as src1
Levels	same as src1

Structures

XieFloBlend sets the XiePhotoElement structure field elemType to xieElemBlend, which identifies the element as a Blend, and sets the fields of the member structure Blend using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef struct {
    int offset_x;
    int offset_y;
    XiePhototag phototag;
} XieProcessDomain;

typedef struct {
    int elemType;
    union {
        ...
        struct {
            XiePhototag src1;
            XiePhototag src2;
            XieConstant src_constant;
            XiePhototag alpha;
```

```
float alpha_constant;
    XieProcessDomain domain;
    unsigned int band_mask;
    } Blend;
    ...
} data;
} XiePhotoElement;
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloMatchIncompatible attributes between src1 and src2 or

alpha is unconstrained or

selected source data are bitonal Invalid *src1*, *src2*, or *alpha*

xieErrNoFloSource xieErrNoFloValue

alpha is zero and alpha_const is outside the range

[0.0,1.0], or

alpha is nonzero and alpha_const is nonpositive

XieFloCompare

XIElib - Photoflo Element Functions

Name

XieFloCompare - specify a Compare element and set its parameters

Syntax

void XieFloCompare (element, src1, src2, domain, constant, operator, combine, band mask)

XiePhotoElement *element;

XiePhototag *src1*; XiePhototag *src2*;

XieProcessDomain *domain;

XieConstant constant;

XieCompareOp operator;

Bool combine;

unsigned int band mask;

Arguments

element Specifies the XiePhotoElement structure to use.

src1 Specifies the first data source.src2 Specifies the second data source.

domain Specifies the subset of source data that will be operated

on.

constant Specifies the constant data source.

operator Specifies the logical predicate operator used in the

comparison.

combine Specifies whether the comparison should be done on a

per-band or on an all-bands basis.

band mask Specifies which bands are to be operated on.

Description

A Compare element takes two data sources or a single data source and a constant and generates a Boolean bitmap output that reflects the results of a pointwise comparison. The output data has a value of one wherever the comparison is true, and a value of zero everywhere else (that is, comparison false or comparison not performed). The comparison may be performed on a perband basis or for all bands taken together.

When two sources are involved, src1 and src2 are the phototags of the elements supplying source data; constant is ignored. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). If the operation is to involve a constant, src1 is one operand, src2 must be zero, and constant is used as the other operand.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by *domain* must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is

to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

operator is the logical predicate operator used in the comparison. The valid operators for the Compare process element are:

Operator	src1 (operator) src2	src1 (operator) constant
xieValLT	src1 src2	src1 constant
xieValLE	src1 src2	src1 constant
xieValEQ	src1 src2	src1 constant
xieValNE	src1 src2	src1 constant
xieValGT	src1 src2	src1 constant
xieValGE	src1 src2	src1 constant

combine is a Boolean that determines whether the comparison should be done on a per-band basis or on an all-bands basis. Only bands selected by <code>band_mask</code> are subject to processing. Other bands present in the image are passed through to the output. For example, a <code>band_mask</code> of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a <code>band_mask</code> of 1112.

If *combine* is True or *src1* is single band, the output data will form a single Boolean bitmap. If *src1* is triple band and *combine* is False, the output data will yield three separate boolean bitmaps (for this case *band_mask* must specify all bands).

If src1 is triple band and combine is True, only the EQ and NE operators are allowed; equality is established for each band selected by $band_mask$, and then the result is logically ANDed to derive equality (inequality is a logical NOT of this result). For this case, width and height must match for all bands selected by $band_mask$.

The relationship between *combine* and data class dependencies is given in the following table:

combine	input class	band_mask	output class
True	True single band n/a		single band
	triple band	selected bands	single band
False	single band	n/a	single band
	triple band	all bands	triple band

Output Attributes

 $\begin{array}{ll} \text{Class} & \text{see Description} \\ \text{Type} & \text{constrained} \\ \text{Width} & \text{same as } \textit{src1} \\ \text{Height} & \text{same as } \textit{src1} \end{array}$

Levels 2 per band (see Description)

Structures

XieFloCompare sets the XiePhotoElement structure field elemType to xieElemCompare, which identifies the element as a Compare, and sets the fields of the member structure Compare using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef struct {
    int offset x;
    int offset y;
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src1;
          XiePhototag src2;
          XieProcessDomain domain;
          XieConstant constant;
          XieCompareOp operator;
          Bool combine;
          unsigned int band mask;
       } Compare;
   } data;
} XiePhotoElement;
/* Definitions of Compare Operators */
#define xieValLT
                                             1
#define xieValLE
#define xieValEQ
                                             3
#define xieValNE
                                             4
                                             5
#define xieValGT
#define xieValGE
                                             6
```

Errors

xieErrNoFloAlloc	Insufficient resources (for example, memory)
xieErrNoFloDomain	Invalid domain
xieErrNoFloMatch	Class differs between src1 and src2 or
	invalid combination of operator and combine or
	triple band, and combine is false, and band mask
	incomplete
xieErrNoFloOperator	Invalid operator
xieErrNoFloSource	Invalid src1 or src2

XieFloConstrain

XIElib - Photoflo Element Functions

Name

XieFloConstrain - specify a Constrain element and set its parameters

Syntax

void XieFloConstrain (element, src, levels, constrain_tech, constrain_param)

XiePhotoElement *element;

XiePhototag *src*; XieLevels *levels*;

XieConstrainTechnique constrain tech;

XiePointer constrain param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

levels Specifies the number of quantization levels desired in

the output data.

constrain tech Specifies the technique to be used when constraining

the data.

constrain param Specifies the list of additional parameters required by

constrain.

Description

A Constrain element applies a quantization model to the image data to convert the data to a fixed number of quantization levels. Application of the quantization model may involve steps such as range shifting, scaling, clipping, and rounding.

src is the phototag of the element supplying source data. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). Levels is the number of quantization levels desired in the output data. constrain_tech specifies the constrain technique to be used when constraining the data. constrain param is the list of additional parameters required by constrain tech.

If the input image is already constrained, the data will be reconstrained.

One of the following standard constrain technique values can be assigned to *constrain tech* :

xieValConstrainClipScale xieValConstrainHardClip

If a vendor defined additional private constrain techniques, the values given to these techniques can be assigned to *constrain_tech*.

Output Attributes

```
Class same as src
Type constrained
Width same as src
Height same as src
Levels levels
```

Structures

XieFloConstrain sets the XiePhotoElement structure field elemType to xieElemConstrain, which identifies the element as a Constrain, and sets the fields of the member structure Constrain using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef unsigned long XieLevels[3];
typedef unsigned XieConstrainTechnique;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          XieLevels levels;
          XieConstrainTechnique constrain_tech;
          XiePointer constrain param;
       } Constrain;
   } data;
} XiePhotoElement;
/* Definitions for ConstrainTechniques */
#define xieValConstrainClipScale
                                             2
#define xieValConstrainHardClip
                                             4
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloSourceInvalid srcxieErrNoFloTechniqueInvalid constrain tech or constrain param

See Also

XieTecClipScale

xielib - Photoflo Element Functions XieFloConvertFromIndex

Name

XieFloConvertFromIndex - specify a ConvertFromIndex element and set its parameters

Syntax

void XieFloConvertFromIndex (element, src, colormap, data_class, precision)
XiePhotoElement *element;

XiePhototag src; Colormap colormap; XieDataClass data_class; unsigned int precision;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

colormap Specifies the Colormap from which to obtain output

pixel values.

data class Specifies whether the output data is single band or

triple band.

precision Specifies the number of bits to be used from colormap's

RGB values.

Description

A ConvertFromIndex element converts Colormap index data into achromatic or trichromatic data.

data_class specifies whether the output data is single band or triple band and can be set to one of the following standard data class values:

xieValSingleBand xieValTripleBand

If *data_class* is single band and a trichromatic *colormap* is specified (static color, pseudo color, true color, or direct color), the gray shade for each pixel is taken from the red values in *colormap*. If *data_class* is triple band and an achromatic *colormap* is specified (static gray or gray scale), the red band will be replicated to populate the green and blue output bands.

The depth of *colormap* must match the Levels attribute of *src* (that is, 2depth must equal Levels).

Output Attributes

Class data_class
Type constrained
Width same as src

Height same as *src*Levels 2*precision* (per band)

Structures

XieFloConvertFromIndex sets the XiePhotoElement structure field elemType to xieElemConvertFromIndex, which identifies the element as a ConvertFromIndex, and sets the fields of the member structure ConvertFromIndex using the arguments in the argument list.

```
typedef unsigned XieDataClass;
typedef unsigned XiePhototag;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          Colormap colormap;
          XieDataClass data class;
          unsigned int precision;
      } ConvertFromIndex;
   } data;
} XiePhotoElement;
/* Definitions of DataClass */
#define xieValSingleBand
#define xieValTripleBand
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloColormapInvalid colormapxieErrNoFloMatchLevels of src do not match depth of colormapxieErrNoFloSourceInvalid srcxieErrNoFloValueInvalid data class or precision

XIElib - Photoflo Element Functions XieFloConvertFromRGB

Name

XieFloConvertFromRGB - specify a ConvertFromRGB element and set its parameters

Syntax

void XieFloConvertFromRGB (element, src, color space, color param)

XiePhotoElement *element;

XiePhototag src;

XieColorspace color_space; XiePointer color_param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data (RGB)

assumed).

color_spacecolor paramSpecifies the technique to be used in the conversion.Specifies the list of additional parameters required by

color space.

Description

A ConvertFromRGB element converts RGB source data to an alternate colorspace.

The source data must be triple band, and all bands must have equal dimensions. The type and levels of the output data are determined by the *color_space*'s technique parameters. All other attributes are inherited from *src*.

ConvertFromRGB techniques define the trichromatic colorspaces known to a ConvertFromRGB element. One of the following standard ConvertFromRGB technique values can be assigned to *color space*:

xieValRGBToCIELab xieValRGBToCIEXYZ xieValRGBToYCbCr xieValRGBToYCC

If a vendor defined additional private ConvertFromRGB techniques, the private technique values given to these techniques can be assigned to *color space*.

Output Attributes

Class triple band

Type color space dependent

Width same as src Height same as src

Levels color space dependent

Structures

XieFloConvertFromRGB sets the XiePhotoElement structure field elemType to xieElemConvertFromRGB, which identifies the element as a ConvertFromRGB, and sets the fields of the member structure ConvertFromRGB using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef unsigned XieColorspace;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XieColorspace color space:
          XiePointer color param;
      } ConvertFromRGB;
   } data;
} XiePhotoElement;
/* Definitions for Colorspace Conversions */
#define xieValRGBToCIELab
                                            2
#define xieValRGBToCIEXYZ
                                            4
#define xieValRGBToYCbCr
                                            6
#define xieValRGBToYCC
                                            8
```

Errors

 $\begin{array}{ll} \text{xieErrNoFloAlloc} & \text{Insufficient resources (for example, memory)} \\ \text{xieErrNoFloMatch} & src \text{ is not triple band } or \\ \text{unequal inter-band dimensions} \\ \text{xieErrNoFloSource} & \text{Invalid } src \\ \text{xieErrNoFloTechnique} & \text{Invalid } color \ space \ \text{or } color \ param \end{array}$

See Also

XieFloConvertToRGB, XieTecRGBToCIELab, XieTecRGBToCIEXYZ, XieTecRGBToYCbCr, XieTecRGBToYCC

XIElib - Photoflo Element Functions XieFloConvertToIndex

Name

XieFloConvertToIndex - specify a ConvertToIndex element and set its parameters

Syntax

XiePointer color alloc param;

Arguments

element Specifies the XiePhotoElement structure to use.

src Specifies the element supplying the constrained source

data.

colormap Specifies the Colormap from which to obtain output

pixel values.

color list Specifies the list where Colormap indices are to be

stored.

notify Specifies whether to enable sending ColorAlloc events.

color alloc tech Specifies the desired color allocation technique.

color alloc param Specifies the list of additional parameters required by

color alloc tech.

Description

A ConvertToIndex element allocates and/or matches colors or gray shades, as required, from a Colormap. It produces pixel indices as output data, and records indices that it allocates in *color list*.

The specified *color_alloc_tech* technique may generate a ColorAlloc event to warn the client that results are of lesser fidelity than desired. *Notify* allows the client to be notified about inferior results from color allocation or matching.

src is the phototag of the element supplying constrained source data. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). Colormap is the Colormap from which colors or gray shades are allocated and/or matched. Color_list is the list where allocated Colormap indices are to be stored. color_alloc_tech specifies the desired color allocation technique. color_alloc_params is the list of additional parameters required by color alloc tech.

color_list is purged of any colors it already contains when photoflo execution begins. Allocated Colormap indices can be freed using XiePurgeColorList,

XieDestroyColorList, or by making *color_list* the target of an active photoflo. Care must be taken to ensure that *color_list* is not referenced by more than one executing photoflo at any time; it is a protocol error to allow more than one executing photoflo access the same color list.

ColorAlloc techniques define the recognized color allocation techniques used by the ConvertToIndex element. One of the following standard ColorAlloc technique values can be assigned to *color alloc tech*:

```
xieValColorAllocDefault
xieValColorAllocAll
xieValColorAllocMatch
xieValColorAllocRequantize
```

If a vendor defined additional private ColorAlloc techniques, the private technique values given to these techniques can be assigned to *color alloc tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Output Attributes

Class	single band
Type	constrained
Width	same as src
Height	same as src

Levels 2depth (that is, colormap depth)

Structures

XieFloConvertToIndex sets the XiePhotoElement structure field elemType to xieElemConvertToIndex, which identifies the element as a ConvertToIndex, and sets the fields of the member structure ConvertToIndex using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef XID XieColorList:
typedef unsigned XieColorAllocTechnique;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          Colormap colormap:
          XieColorList color list;
          Bool notify:
          XieColorAllocTechnique color alloc tech;
          XiePointer color alloc param;
       } ConvertToIndex;
   } data:
} XiePhotoElement;
/* Definitions for ColorAlloc Techniques */
```

#define xieValColorAllocDefault0#define xieValColorAllocAll2#define xieValColorAllocMatch4#define xieValColorAllocRequantize6

Errors

xieErrNoFloAccess color list already being used by another active photoflo

xieErrNoFloAlloc Insufficient resources (for example, memory)

 $egin{array}{ll} {\it xieErrNoFloColorlist} & {\it Invalid\ color_list} \\ {\it xieErrNoFloColormap} & {\it Invalid\ colormap} \\ \end{array}$

xieErrNoFloMatch Unequal inter-band dimensions

xieErrNoFloSource Invalid src

 $xie Err No Flo Technique \quad Invalid \ color_alloc_tech \ or \ color_alloc_param$

See Also

XieCreateColorList, XiePurgeColorList, XieDestroyColorList XieTecColorAllocAll, XieTecColorAllocMatch, XieTecColorAllocRequantize

XIElib - Photoflo Element Functions

XieFloConvertToRGB

Name

XieFloConvertToRGB - specify a ConvertToRGB element and set its parameters

Syntax

void XieFloConvertToRGB (element, src, color_space, color_param)

XiePhotoElement *element;

XiePhototag src;

XieColorspace color_space; XiePointer color_param;

Arguments

elementSpecifies the XiePhotoElement structure to use.srcSpecifies the element supplying source data.color_spaceSpecifies the technique that will be used for the

conversion.

color param Specifies the list of additional parameters required by

color space.

Description

A ConvertToRGB element converts alternate colorspace source data into RGB data.

The source data must be triple band, and all bands must have equal dimensions. The type and levels of the output data are determined by the *color_space*'s technique parameters. All other attributes are inherited from *src*.

ConvertToRGB techniques define the trichromatic colorspaces known to a ConvertToRGB element. One of the following standard ConvertFromRGB technique values can be assigned to *color space*:

xieValCIELabToRGB xieValCIEXYZToRGB xieValYCbCrToRGB xieValYCCToRGB

If a vendor defined additional private ConvertToRGB techniques, the private technique values given to these techniques can be assigned to *color space*.

Output Attributes

Class triple band

Type color space dependent

Width same as src Height same as src

Levels color space dependent

Structures

XieFloConvertToRGB sets the XiePhotoElement structure field elemType to xieElemConvertToRGB, which identifies the element as a ConvertToRGB, and sets the fields of the member structure ConvertToRGB using the arguments in the argument list.

```
typedef unsigned XieColorspace;
typedef unsigned XiePhototag;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XieColorspace color space;
          XiePointer color param;
      } ConvertToRGB;
   } data;
} XiePhotoElement;
/* Definitions for Colorspace Conversions */
#define xieValCIELabToRGB
                                            2
#define xieValCIEXYZToRGB
                                            4
                                            6
#define xieValYCbCrToRGB
#define xieValYCCToRGB
                                            8
```

Errors

 $\begin{array}{ll} \text{xieErrNoFloAlloc} & \text{Insufficient resources (for example, memory)} \\ \text{xieErrNoFloMatch} & src \text{ is not triple band } or \\ \text{unequal inter-band dimensions} \\ \text{xieErrNoFloSource} & \text{Invalid } src \\ \text{xieErrNoFloTechnique} & \text{Invalid } color \ space \ \text{or } color \ param \end{array}$

See Also

XieTecCIELabToRGB, XieTecCIEXYZToRGB, XieTecYCbCrToRGB, XieTecYCCToRGB, XieConvertFromRGB

XieFloConvolve

XIElib - Photoflo Element Functions

Name

XieFloConvolve - specify a Convolve element and set its parameters

Syntax

void XieFloConvolve (element, src, domain, kernel, kernel_size, band_mask, convolve tech, convolve param)

XiePhotoElement *element;

XiePhototag *src*;

XieProcessDomain *domain;

float *kernel;

int kernel_size;

unsigned int band_mask;

XieConvolveTechnique convolve tech;

XiePointer convolve param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

domain Specifies the subset of the image that will be operated

on.

kernel Specifies the coefficients used in the convolution

process.

kernel size Specifies the dimension of kernel.

band mask Specifies which bands are to be operated on.

convolve_tech Specifies the technique for handling edge conditions. Specifies the list of additional parameters required by

convolve tech.

Description

A Convolve element produces output data by convolving each input pixel value (and surrounding area) with the specified convolution kernel.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by domain must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

kernel represents a square array of float data that has odd dimensions. Thus, a single dimension is used to specify *kernel_size*.

Only bands selected by the *band_mask* are subject to processing. Other bands present in the image are passed through to the output. For example, a *band_mask* of 0012 indicates that only the "least significant band" would be

processed; operating on all bands requires a *band_mask* of 1112. Using *band_mask* to select source data that have two (2) or less levels is not permitted.

All output data attributes are inherited from the source data.

Convolve techniques provide various methods of handling edge conditions. These techniques determine what pixel values are used when Convolve requires data beyond the image bounds. One of the following standard convolve technique values can be assigned to *convolve tech*:

```
xieValConvolveDefault
xieValConvolveConstant
xieValConvolveReplicate
```

If a vendor defined additional private convolve techniques, the private technique values given to these techniques can be assigned to *convolve tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined above or a private technique.

Output Attributes

Class	same	as	src
Type	same	as	src
Width	same	as	src
Height	same	as	src
Levels	same	as	src

Structures

XieFloConvolve sets the XiePhotoElement structure field elemType to xieElemConvolve, which identifies the element as a Convolve, and sets the fields of the member structure Convolve using the arguments in the argument list.

```
typedef unsigned XieConvolveTechnique;
typedef unsigned XiePhototag;
typedef struct {
    int offset x;
    int offset v:
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          XieProcessDomain domain;
          float *kernel;
          int kernel size;
          unsigned int band mask;
          XieConvolveTechnique convolve tech;
          XiePointer convolve param;
       } Convolve;
```

```
} data;
} XiePhotoElement;

/* Definitions for ConvolveTechniques */
#define xieValConvolveDefault 0
#define xieValConvolveConstant 2
#define xieValConvolveReplicate 4
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloDomain Invalid domain

xieErrNoFloMatch Selected source data are bitonal

xieErrNoFloSource Invalid src

See Also

XieTecConvolveConstant

XieFloDither

XIElib - Photoflo Element Functions

Name

XieFloDither - specify a Dither element and set its parameters

Syntax

void XieFloDither (element, src, band_mask, levels, dither_tech, dither_param)
 XiePhotoElement *element;
 XiePhototag src;
 unsigned int band_mask;
 XieLevels levels;
 XieDitherTechnique dither tech;

XiePointer dither param;

Arguments

elementSpecifies the XiePhotoElement structure to use.srcSpecifies the element supplying source data.band_maskSpecifies which bands are to be operated on.

levels Specifies the number of levels desired in the output

data.

dither tech Specifies the desired dither technique.

dither param Specifies the list of additional parameters required by

 $dither_tech.$

Description

The Dither element is used to reduce the number of quantization levels in an image. It accomplishes this by affecting adjacent pixels (area affect) to make up for the lack of depth resolution.

Only bands selected by the <code>band_mask</code> are subject to processing. Other bands present in the image are passed through to the output. For example, a <code>band_mask</code> of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a <code>band_mask</code> of 1112. Using <code>band_mask</code> to select source data that have two (2) or less levels is not permitted.

The source data must be constrained.

Dither techniques define the technique that can be used to dither an image. One of the following standard dither technique values can be assigned to *dither tech*:

xieValDitherDefault xieValDitherErrorDiffusion xieValDitherOrdered

If a vendor defined additional private dither techniques, the private technique values given to these techniques can be assigned to *dither_tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Output Attributes

Class same as src Type constrained Width same as src Height same as src Levels levels

Structures

XieFloDither sets the XiePhotoElement structure field elemType to xieElemDither, which identifies the element as a Dither, and sets the fields of the member structure Dither using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef unsigned long XieLevels[3];
typedef unsigned XieDitherTechnique;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          XieLevels levels:
          unsigned int band mask;
          XieDitherTechnique dither tech;
          XiePointer dither param;
       } Dither;
   } data;
} XiePhotoElement;
/* Definitions for DitherTechniques */
#define xieValDitherDefault
#define xieValDitherErrorDiffusion
#define xieValDitherOrdered
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

Invalid domain xieErrNoFloDomain

xieErrNoFloMatchUnconstrained src data or

selected source data are bitonal

0 2

4

xieErrNoFloSource Invalid src

xieErrNoFloTechnique Invalid dither tech or dither param

xieErrNoFloValue Invalid output levels: less than two or greater than src

levels

See Also

XieTecDitherOrdered

XieFloGeometry

XIElib - Photoflo Element Functions

Name

XieFloGeometry - specify a Geometry element and set its parameters

Syntax

void XieFloGeometry (element, src, width, height, coefficients, constant, band mask, sample tech, sample param)

XiePhotoElement *element;

XiePhototag src;

unsigned int width;

unsigned int height;

float coefficients[6];
XieConstant constant;

unsigned int band mask;

XieGeometryTechnique sample tech;

XiePointer sample param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

width Specifies the horizontal dimension of the output data.
 height Specifies the vertical dimension of the output data.
 coefficients Specifies an affine transformation to be applied to pixels

in src.

constant Specifies the fill value used for output pixels that do not

map back to a *src* pixel.

band mask Specifies which bands are to be operated on.

sample tech Specifies the technique to be used for retrospectively

resampling src.

sample param Specifies the list of additional parameters required by

sample tech.

Description

A Geometry element is used to perform geometric transformations on image data. Linear geometric resampling operations are implemented, such as: crop, mirror, scale, shear, rotate, translate, and combinations thereof.

A Geometry element can be visualized as stepping through each possible output pixel location in turn and computing the location from which to obtain each input pixel value. Each pixel (x',y') in the output image is mapped to the coordinate location (x,y) in src by:

The coordinate mapping *coefficients* (a,b,c,d,tx,ty), together with the output *width* and *height*, fully specify the geometric transformation. The following briefly (and approximately) summarizes the intuitive role of each parameter:

- a, d Scaling parameters. Increasing a and d will make the output image appear smaller, whereas decreasing them will make the output pixels appear larger.
- b, c Rotation/skew parameters. If b and c are zero, the output image will be a rectangular scaling of the input image. If a and d are both zero, b is one, and c is negative one, the image will appear rotated. The magnitude of b and c will affect scaling as well if a and d are zero. If more than two of (a,b,c,d) are nonzero, the effect is complicated. The image may appear skewed and scaled.
- tx, ty Translation parameters. Used to specify the offset between input and output coordinate systems.
- width, height These specify the output image dimensions of the selected band(s). Note that increasing the output image height and width over the input image size will not by itself cause magnification if a and d are one (1) and b and c are zero (0), the output image will have the same appearance as the input, except that the borders will shrink or expand (as determined by width and height) and new areas of the image will be filled with *constant*.

The region to be cropped in the input image is implicitly defined by the dimensions of the output image and the mapping from output to input coordinates. Depending on the size of the input and output images, the amount of scaling specified, and the amount of translation in the mapping, pixels in the output image may map off the edge of the input image and the *constant* value is used.

Trichromatic image bands can be operated individually, all together, or in any combination, using <code>band_mask</code>. Since applying the same (a,b,c,d,tx,ty) mapping to inputs with diverse sizes will specify different transformations, operating on all bands in unison (<code>band_mask</code> of 1112) is most appropriate if the dimensions of all bands are equal.

Often a given output pixel location (x',y') will not correspond exactly to a single pixel in the input image. The *sample_tech* technique is used to determine how the input data will be interpolated to produce each output pixel value. One of the following standard geometry technique values can be assigned to *sample tech*:

xieValGeomDefault xieValGeomAntialias xieValGeomAntialiasByArea xieValGeomAntialiasByLPF xieValGeomBilinearInterp xieValGeomGaussian xieValGeomNearestNeighbor

If a vendor defined additional private geometry techniques, the private technique values given to these techniques can be assigned to *sample_tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Output Attributes

```
\begin{array}{ll} \text{Class} & \text{same as } \textit{src} \\ \text{Type} & \text{same as } \textit{src} \\ \text{Width} & \textit{width} \\ \text{Height} & \textit{height} \\ \text{Levels} & \text{same as } \textit{src} \end{array}
```

Structures

XieFloGeometry sets the XiePhotoElement structure field elemType to xieElemGeometry, which identifies the element as a Geometry, and sets the fields of the member structure Geometry using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef unsigned XieGeometryTechnique;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          unsigned int width;
          unsigned int height;
          float coefficients[6]:
          XieConstant constant;
          unsigned int band mask;
          XieGeometryTechnique sample tech;
          XiePointer sample param;
      } Geometry;
   } data;
} XiePhotoElement;
/* Definitions for GeometryTechniques */
#define xieValGeomDefault
                                            0
#define xieValGeomAntialias
                                            2
#define xieValGeomAntialiasByArea
                                            4
#define xieValGeomAntialiasByLPF
                                            6
#define xieValGeomBilinearInterp
                                            8
#define xieValGeomGaussian
                                            10
#define xieValGeomNearestNeighbor
                                            12
```

Errors

xieErrNoFloAlloc	Insufficient resources (for example, memory)
xieErrNoFloSource	Invalid src
xieErrNoFloTechnique	Invalid sample_tech or sample_param
xieErrNoFloValue	Invalid coefficients

See Also

Name

XieFloLogical - specify a Logical element and set its parameters

Syntax

void XieFloLogical (element, src1, src2, domain, constant, operator, band_mask)
 XiePhotoElement *element;
 XiePhototag src1;
 XiePhototag src2;
 XieProcessDomain *domain;
 XieConstant constant;
 unsigned long operator;

unsigned int band_mask;
Arguments

element Specifies the XiePhotoElement structure to use.

src1 Specifies the first data source.src2 Specifies the second data source.

domain Specifies the subset of source data that will be operated

on.

constantSpecifies the constant data source.operatorSpecifies the logical operator to be used.band_maskSpecifies which bands are to be operated on.

Description

A Logical element performs per-pixel bitwise operations on a single data source, or between two data sources, or between a single data source and a constant.

When two sources are involved, src1 and src2 are the phototags of the elements supplying source data; constant is ignored. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). If the operation is to involve a constant, src1 is one operand, src2 must be zero, and constant is used as the other operand.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by *domain* must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

The value of *operator* matches the GC-function values defined by the core protocol specification for CreateGC. The output of a Logical element is determined by the number of data sources and *operator*:

GC function	monadic operation	dyadic operation

Clear	0	0
And	constant AND src1	src2 AND src1
AndReverse	constant AND (NOT src1)	src2 AND (NOT src1)
Copy	constant	src2
AndInverted	(NOT constant) AND src1	(NOT src2) AND src1
NoOp	src1	src1
Xor	constant XOR src1	src2 XOR src1
Or	constant OR src1	src2 OR src1
Nor	(NOT constant) AND (NOT	(NOT src2) AND (NOT
	src1)	src1)
Equiv	(NOT constant) XOR src1	(NOT src2) XOR src1
Invert	NOT src1	NOT src1
OrReverse	constant OR (NOT src1)	src2 OR (NOT src1)
CopyInverted	NOT constant	NOT src2
OrInverted	(NOT constant) OR src1	(NOT src2) OR src1
Nand	(NOT constant) OR (NOT	(NOT src2) OR (NOT
	src1)	src1)
Set	1	1

Only bands selected by the *band_mask* are subject to processing. Other bands present in the image are passed through to the output. For example, a *band_mask* of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a *band_mask* of 1112.

Output Attributes

Class	same as <i>src1</i>
Type	constrained
Width	same as <i>src1</i>
Height	same as <i>src1</i>
Levels	same as src1

Structures

XieFloLogical sets the XiePhotoElement structure field elemType to xieElemLogical, which identifies the element as a Logical, and sets the fields of the member structure Logical using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef struct {
    int offset_x;
    int offset_y;
        XiePhototag phototag;
} XieProcessDomain;

typedef struct {
    int elemType;
    union {
        ...
        struct {
            XiePhototag src1;
            XiePhototag src2;
        }
}
```

```
XieProcessDomain domain;
XieConstant constant;
int operator;
unsigned int band_mask;
} Logical;
...
} data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloDomain Invalid domain

xieErrNoFloMatch Class or levels differ between src1 and src2, or

levels is not a power of 2, or src1 or src2 in not constrained

 $egin{array}{ll} {\it xieErrNoFloOperator} & {\it Invalid\ operator} \\ {\it xieErrNoFloSource} & {\it Invalid\ src1\ or\ src2} \\ \end{array}$

${\bf XiElib - Photoflo \; Element \; Functions } \quad {\bf XieFloMatchHistogram}$

Name

XieFloMatchHistogram - specify a MatchHistogram element and set its parameters

Syntax

void XieFloMatchHistogram (element, src, domain, shape, shape param)

XiePhotoElement *element;

XiePhototag src;

XieProcessDomain *domain; XieHistogramShape shape; XiePointer shape_param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

domain Specifies the subset of source data that will be operated

on.

shape Specifies the form of the desired output data histogram. Specifies the list of additional parameters required by

shape.

Description

A MatchHistogram element produces output data that differ from the source data in terms of its pixel value distribution, or histogram. It allows the client to specify the desired shape of the resulting data's histogram (algorithmic description of resulting histogram shape).

The source data must be constrained and single band, and it must have three or more levels.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by domain must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. Only data that intersects with the subset specified by domain is included in the histogram, and only that data will be affected in the result of the histogram matching operation: all other data will pass through unchanged. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

Histogram Shape defines the various match-histogram shape techniques that can be requested by a MatchHistogram element. One of the following standard match-histogram shape technique values can be assigned to *shape*:

xieValHistogramFlat xieValHistogramGaussian xieValHistogramHyperbolic If a vendor defined additional private match-histogram shape techniques, the private technique values given to these techniques can be assigned to *shape*.

Output Attributes

Class	single band
Type	constrained
Width	same as <i>src</i>
Height	same as <i>src</i>
Levels	same as <i>src</i>

Structures

XieFloMatchHistogram sets the XiePhotoElement structure field elemType to xieElemMatchHistogram, which identifies the element as a MatchHistogram, and sets the fields of the member structure MatchHistogram using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef unsigned XieHistogramShape;
typedef struct {
    int offset x;
    int offset y;
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XieProcessDomain domain;
          XieHistogramShape shape;
          XiePointer shape param;
      } MatchHistogram;
   } data;
} XiePhotoElement;
/* Definitions for GeometryTechniques */
#define xieValGeomDefault
                                            0
                                            2
#define xieValGeomAntialias
#define xieValGeomAntialiasByArea
                                            4
#define xieValGeomAntialiasBvLPF
                                            6
#define xieValGeomBilinearInterp
                                            8
#define xieValGeomGaussian
                                            10
#define xieValGeomNearestNeighbor
                                            12
```

Errors

xieErrNoFloAlloc	Insufficient resources (for example, memory)
xieErrNoFloDomain	Invalid domain
xieErrNoFloMatch	Invalid <i>src</i> data: unconstrained, triple band, or bitonal
xieErrNoFloSource	Invalid src
xieErrNoFloTechnique	Invalid shape or shape param

See Also

 ${\it Xie TecHistogram Gaussian, Xie TecHistogram Hyperbolic}$

XieFloMath

XIElib - Photoflo Element Functions

Name

XieFloMath - specify a Math element and set its parameters

Syntax

void XieFloMath (element, src, domain, operator, band_mask)

XiePhotoElement *element;

XiePhototag src;

XieProcessDomain *domain:

XieMathOp operator; unsigned int band mask;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

domain Specifies the subset of source data that will be operated

on.

operator Specifies the mathematical operation to be applied.

band mask Specifies which bands are to be operated on.

Description

A Math element applies a single operand mathematical operation to the source data on a point-wise basis.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by *domain* must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

Pixel computations that would lead to errors will yield valid server-dependent values (for example, the log of a constrained pixel value of zero might result in a value of zero). Only bands selected by the <code>band_mask</code> are subject to processing. Other bands present in the image are passed through to the output. For example, a <code>band_mask</code> of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a <code>band_mask</code> of 1112. Using <code>band_mask</code> to select source data that have two (2) or less levels is not permitted.

The following valid mathematical operations that can be invoked through the Math element:

Operator	Meaning
xieValExp	exponential
xieValLn	natural logarithm
xieValLog2	logarithm base 2

xieValLog10	logarithm base 10
xieValSquare	square
xieValSqrt	square root

All output data attributes are inherited from the source data.

Output Attributes

Class	same as src
Type	same as src
Width	same as src
Height	same as src
Levels	same as src

Structures

XieFloMath sets the XiePhotoElement structure field elemType to xieElemMath, which identifies the element as a Math, and sets the fields of the member structure Math using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef unsigned XieMathOp;
typedef struct {
    int offset x;
    int offset v:
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XieProcessDomain domain;
          XieMathOp operator;
          unsigned int band mask;
       } Math;
   } data;
} XiePhotoElement;
/* Definitions of Math Operators */
#define xieValExp
#define xieValLn
                                             2
#define xieValLog2
                                             3
#define xieValLog10
                                             5
#define xieValSquare
                                             6
#define xieValSqrt
```

Errors

xieErrNoFloAlloc	Insufficient resources (for example, memory)
xieErrNoFloDomain	Invalid domain
xieErrNoFloMatch	Selected source data are bitonal
xieErrNoFloSource	Invalid src

xieErrNoFloOperator Invalid operator

XieFloPasteUp

XIElib - Photoflo Element Functions

Name

XieFloPasteUp - specify a PasteUp element and set its parameters

Syntax

void XieFloPasteUp (element, width, height, constant, tiles, tile_count)
 XiePhotoElement *element;
 unsigned int width;
 unsigned int height;
 XieConstant constant;
 XieTile *tiles
 unsigned int tile_count;

Arguments

elementSpecifies the XiePhotoElement structure to use.widthSpecifies the full horizontal extent of the output data.heightSpecifies the full vertical extent of the output data.constantSpecifies the fill value for output regions that do not

intersect the regions defined in tiles.

tiles Specifies a list of tile descriptors.

tile_count Specifies the number of tile descriptors in tiles.

Description

A PasteUp element is an N-input translate operation that outputs data constructed from various source data tiles or a constant value.

Each of the *tiles* specifies a src (the *phototag* of the element supplying source data), and the coordinates, dst_x and dst_y, where the tile belongs in the output data. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1).

Each region of the output data is defined by a tile's destination coordinates, dst_x and dst_y, and its src dimensions. For output regions where no tile provides input, the value of *constant* is used. If tiles overlap, a stacking-order rule defines which pixel value will be output: the last tile involved in the overlap in the list of *tiles* will provide the output pixel.

At least one tile must be supplied. Except for *width* and *height*, all attributes of each source tile must match. In addition, for triple band input, inter-band dimensions within each *tiles* must match.

Output Attributes

Class same as tiles
Type same as tiles

Width width

Height height Levels same as tiles

Structures

XieFloPasteUp sets the XiePhotoElement structure field elemType to xieElemPasteUp, which identifies the element as a PasteUp, and sets the fields of the member structure PasteUp using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef float XieConstant[3];
typedef struct {
   XiePhototag src;
   int dst x;
   int dst y;
} XieTile;
typedef struct {
   int elemType;
   union {
       struct {
          unsigned int width;
          unsigned int height;
          XieConstant constant:
          XieTile *tiles;
          unsigned int tile count;
       } PasteUp;
   } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory) Incompatible attributes between tiles or xieErrNoFloMatch unequal inter-band dimensions within a tile

xieErrNoFloSource Invalid source tiles or no tiles were specified

See Also

XieFreePasteUpTiles

XieFloPoint

XIElib - Photoflo Element Functions

Name

XieFloPoint - specify a Point element and set its parameters

Syntax

void XieFloPoint (element, src, domain, lut, band_mask)
 XiePhotoElement *element;
 XiePhototag src;
 XieProcessDomain *domain;
 XieLut lut;
 unsigned int band mask;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying source data.

domain Specifies the subset of source data that will be operated

on.

lut Specifies the LUT resource supplying the lookup table.

band mask Specifies which bands are to be operated on.

Description

A Point element maps source pixel values to output pixel values using a lookup table (LUT).

src is the phototag of the element supplying constrained source data. A phototag is the position or index of an element within an array of elements used to specify a photoflo; the first element in the array has a phototag value of one (1). Lut is the phototag of the ImportClientLUT or ImportLUT element supplying the lookup table data.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by *domain* must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset_y fields are ignored.

band_mask specifies which bands are to be operated on (all bands must be specified if *lut* is single band and *src* is triple band). For example, a *band_mask* of 0012 indicates that only the "least significant band" would be processed; operating on all bands requires a *band_mask* of 1112.

The output is constrained, with the width and height taken from src and class and levels taken from lut. When src is single band and lut is triple band, for the bands that are indicated by $band_mask$, the output bands are remapped through their respective lut bands, whereas the other bands are just replications of the

single *src* band. If *domain* is used, the class and levels of *lut* must match those of *src*.

Each *lut* array must contain sufficient entries so that all potential pixel values found in *src* can form a valid index into the array. Generally each *src* pixel value is used directly as an index into a *lut* array. When triple band *src* data are remapped through a single band *lut*, however, pixel values from all three *src* bands are combined to form an array index; for this case, width and height must match for all bands.

When a single band *lut* is used to remap triple band *src* data, the following presents the algorithm for computing combined array indices:

LUT band order	LUT indexing algorithm for combining pixel values
LSFirst	<pre>index = value[0] + value[1] x levels[0] + value[2] x levels[0] x levels[1]</pre>
MSFirst	index = value[2] + value[1] x levels[2] + value[0] x levels[2] x levels[1]

Output Attributes

Class	same as <i>lut</i>
Type	constrained
Width	same as <i>src</i>
Height	same as <i>src</i>
Levels	same as <i>lut</i>

Structures

XieFloPoint sets the XiePhotoElement structure field elemType to xieElemPoint, which identifies the element as a Point, and sets the fields of the member structure Point using the arguments in the argument list.

```
typedef XID XieLut;
typedef unsigned XiePhototag;
typedef struct {
    int offset x;
    int offset v:
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src:
          XieProcessDomain domain:
          XieLut lut:
          unsigned int band mask;
       } Point;
   } data;
} XiePhotoElement:
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloDomain Invalid domain

xieErrNoFloMatch Unconstrained src data, or

lut does not contain enough entries, or

lut is single band and src is triple band, but band mask

is incomplete, or

domain is being used, but lut class or levels do not

match those of src

xieErrNoFloSource Invalid src or lut

See Also

XieFloImportLUT, XieFloImportClientLUT

XIElib - Photoflo Element Functions

Name

XieFloUnconstrain - specify an unconstrain element and set its parameters

Syntax

```
void XieFloUnconstrain (element, src)
    XiePhotoElement *element;
    XiePhototag src;
```

Arguments

elementsrcSpecifies the XiePhotoElement structure to use.Specifies the element supplying constrained source

data.

Description

An Unconstrain element produces unconstrained output data from constrained input data.

Output Attributes

Class	same as <i>src</i>
Type	unconstrained
Width	same as src
Height	same as src
Levels	unknown

Structures

XieFloUnconstrain sets the XiePhotoElement structure field elemType to xieElemUnconstrain, which identifies the element as an Unconstrain, and sets the fields of the member structure Unconstrain using the arguments in the argument list.

```
typedef unsigned XiePhototag;
```

```
typedef struct {
   int elemType;
   union {
     ...
     struct {
         XiePhototag src;
     } Unconstrain;
     ...
   } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc xieErrNoFloMatch xieErrNoFloSource Insufficient resources (for example, memory) Unconstrained src data Invalid src

See Also

XieFloConstrain

XIElib - Photoflo Element

Functions

XieFloExportClientHistogram

Name

XieFloExportClientHistogram - specify an ExportClientHistogram element and set its parameters

Syntax

void XieFloExportClientHistogram (element, src, domain, notify)

XiePhotoElement *element;

XiePhototag src;

XieProcessDomain *domain;

XieExportNotify notify;

Arguments

element Specifies the XiePhotoElement structure to use.

src Specifies the element supplying single band constrained

source data.

domain Specifies the subset of the source data from which the

distribution will be generated.

notify Specifies whether to enable sending an ExportAvailable

event.

Description

An ExportClientHistogram element generates a histogram of the pixel values found in the source data. It prepares histogram data that can be retrieved by the client using XieGetClientData. An event can be requested that will notify the client when histogram data becomes available.

The data generated for the client is a list of XieHistogramData where each entry consists of a value (that is, a pixel value) followed by the count of pixels found with that value. If the number of pixels for a given value exceeds the capacity of count, that count will be returned at the maximum value (that is, 232 - 1). Pixel values that are not found in the data are not included in the histogram data: no entries are returned where count is zero.

In order to specify a subset of source data that will be operated on, the phototag, offset_x, and offset_y fields of the XieProcessDomain structure pointed to by domain must be supplied; XIElib does not provide a convenience function to create and/or fill in an XieProcessDomain structure. Only data that intersects with the subset specified by domain is included in the histogram. If the entire source data is to be operated on, a pointer to an XieProcessDomain structure must still be provided, with the phototag field set to zero (0); the offset_x and offset y fields are ignored.

One of three standard export notify values can be assigned to *notify*:

xieValDisable xieValFirstData If *notify* was specified as xieValFirstData, this event will be sent only the first time data become available; otherwise, if xieValNewData was specified, this event will be generated each time the amount of data available changes from zero to nonzero.

Structures

XieFloExportClientHistogram sets the XiePhotoElement structure field elemType to xieElemExportClientHistogram, which identifies the element as an ExportClientHistogram, and sets the fields of the member structure ExportClientHistogram using the arguments in the argument list.

```
typedef unsigned XieExportNotify;
typedef unsigned XiePhototag;
typedef struct {
    int offset x;
    int offset y;
    XiePhototag phototag;
} XieProcessDomain;
typedef struct {
   unsigned long value;
   unsigned long count;
} XieHistogramData;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          XieProcessDomain domain;
          XieExportNotify notify:
       } ExportClientHistogram;
   } data;
} XiePhotoElement;
/* Definitions of ExportNotify */
#define xieValDisable
                                             1
                                             2
#define xieValFirstData
#define xieValNewData
                                             3
```

Errors

 $\begin{array}{lll} \text{xieErrNoFloAlloc} & \text{Insufficient resources (for example, memory)} \\ \text{xieErrNoFloDomain} & \text{Invalid } domain \\ \text{xieErrNoFloMatch} & \text{Unconstrained } src \text{ data } or \\ \text{triple band } src \text{ data} \\ \text{xieErrNoFloSource} & \text{Invalid } src \\ \text{xieErrNoFloValue} & \text{Invalid } notify \\ \end{array}$

See Also

XieGetClientData

XIElib - Photoflo Element Functions XieFloExportClientLUT

Name

XieFloExportClientLUT - specify an ExportClientLUT element and set its parameters

Syntax

 $void\ XieFloExportClientLUT\ (element,\ src,\ band_order,\ notify,\ start,\ length)$

XiePhotoElement *element;

XiePhototag src;

XieOrientation band_order; XieExportNotify notify;

XieLTriplet *start*; XieLTriplet *length*;

Arguments

elementsrcSpecifies the XiePhotoElement structure to use.Specifies the element supplying lookup table data.

band order Specifies the order of triple band arrays.

notify Specifies whether to enable sending an ExportAvailable

event.

start Specifies the index of the first array entry that should

be returned.

length Specifies the number of array entries that should be

returned.

Description

An ExportClientLUT element allows data imported from an ImportLUT or an ImportClientLUT element to be retrieved by the client. The actual transport of lookup table data through the protocol stream is requested using XieGetClientData.

One of three standard export notify values can be assigned to *notify*:

xieValDisable xieValFirstData xieValNewData

If *notify* was specified as xieValFirstData, this event will be sent only the first time data become available; otherwise, if xieValNewData was specified, this event will be generated each time the amount of data available changes from zero to nonzero.

band_order is the order in which triple band arrays are transmitted through the protocol stream. One of the following standard orientation values can be assigned to band_order:

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: for example, red is the least significant band of RGB data. For band-by-plane data, <code>band_order</code> specifies whether this band corresponds with the least significant or most significant LUT array. Each array is transported as a separate data stream:

band	LSFirst	MSFirst
0	R7R6 R5R4 R3R2R1R0	B7B6B5B4B3B2B1B0
1	G7 G6G 5G4G 3G2 G1G0	G7 G6G 5G 4G 3G2 G1G 0
2	B7B6B5B4B3B2B1B0	R7R6 R5R4 R3R2R1R0

The size of each array entry is either 1, 2, or 4 bytes: the smallest size into which the output quantization levels can be stored. When array entries require multiple bytes, the byte order per entry is determined in the same manner as other numeric data: it is the byte orientation established at core X connection setup time.

Structures

XieFloExportClientLUT sets the XiePhotoElement structure field elemType to xieElemExportClientLUT, which identifies the element as an ExportClientLUT, and sets the fields of the member structure ExportClientLUT using the arguments in the argument list.

```
typedef unsigned XieExportNotify;
typedef unsigned XieOrientation;
typedef unsigned long XieLTriplet[3]:
typedef unsigned XiePhototag;
typedef struct {
   int elemType;
   union {
       struct {
          XiePhototag src;
          XieOrientation band order:
          XieExportNotify notify;
          XieLTriplet start;
          XieLTriplet length:
       } ExportClientLUT;
   } data;
} XiePhotoElement;
/* Definitions of ExportNotify */
#define xieValDisable
                                              1
#define xieValFirstData
                                              2
                                              3
#define xieValNewData
/* Definitions of Orientation Types */
#define xieValLSFirst
                                              1
#define xieValMSFirst
                                              2
```

Errors

xieErrNoFloAlloc

Insufficient resources (for example, memory) start + length exceeds number of entries in an array Invalid srcxieErrNoFloMatch

xie Err No Flo Source

Invalid *notify* or *band order* xieErrNoFloValue

See Also

XieFloImportLUT, XieFloImportClientLUT, XieGetClientData

XIElib - Photoflo Element Functions XieFloExportClientPhoto

Name

XieFloExportClientPhoto - specify an ExportClientPhoto element and set its parameters

Syntax

void XieFloExportClientPhoto (element, src, notify, encode_tech, encode_param)

XiePhotoElement *element;

XiePhototag src;

XieExportNotify notify;

XieEncodeTechnique encode tech;

XiePointer encode param;

Arguments

element Specifies the XiePhotoElement structure to use.src Specifies the element supplying constrained data.

notify Specifies whether to enable sending an ExportAvailable

event.

encode tech Specifies the technique to compress or format the

exported data.

encode_param Specifies the list of additional parameters required by

encode tech.

Description

An ExportClientPhoto element makes image data available to the protocol stream. The attributes of the exported data are determined by the attributes of the source data. The format of the data is specified by the <code>encode_tech</code> technique and <code>encode_param</code>. The actual transport of image data through the protocol stream is requested using XieGetClientData.

One of three standard export notify values can be assigned to *notify*:

xieValDisable xieValFirstData xieValNewData

If *notify* was specified as xieValFirstData, this event will be sent only the first time data become available; otherwise, if xieValNewData was specified, this event will be generated each time the amount of data available changes from zero to nonzero.

Encode techniques define the techniques that can be used to compress an image or format it as uncompressed data. One of the following standard encode technique values can be assigned to *encode tech*:

xieValEncodeServerChoice xieValEncodeUncompressedSingle xieValEncodeUncompressedTriple

```
xieValEncodeG31D
xieValEncodeG32D
xieValEncodeG42D
xieValEncodeJPEGBaseline
xieValEncodeJPEGLossless
xieValEncodeTIFF2
xieValEncodeTIFFPackBits
```

If a vendor defined additional private encode techniques, the private technique values given to these techniques can be assigned to *encode tech*.

Structures

XieFloExportClientPhoto sets the XiePhotoElement structure field elemType to xieElemExportClientPhoto, which identifies the element as an ExportClientPhoto, and sets the fields of the member structure ExportClientPhoto using the arguments in the argument list.

```
typedef unsigned XieExportNotify;
typedef unsigned XiePhototag;
typedef unsigned XieEncodeTechnique;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XieExportNotify notify:
          XieEncodeTechnique encode tech;
          XiePointer encode param;
      } ExportClientPhoto;
   } data:
} XiePhotoElement;
/* Definitions of ExportNotify */
#define xieValDisable
                                            1
                                            2
#define xieValFirstData
                                            3
#define xieValNewData
/* Definitions for EncodeTechniques */
#define xieValEncodeServerChoice
                                            1
                                            2
#define xieValEncodeUncompressedSingle
#define xieValEncodeUncompressedTriple
                                            3
#define xieValEncodeG31D
                                            4
#define xieValEncodeG32D
                                            6
                                            8
#define xieValEncodeG42D
#define xieValEncodeJPEGBaseline
                                            10
#define xieValEncodeIPEGLossless
                                            12
#define xieValEncodeTIFF2
                                            14
#define xieValEncodeTIFFPackBits
                                            16
```

Errors

xieErrNoFloAlloc Insufficient res

Insufficient resources (for example, memory)

xieErrNoFloMatch Unconstrained src data

xieErrNoFloSource Invalid src

xieErrNoFloTechnique Invalid encode tech or encode param

xieErrNoFloValue Invalid notify

See Also

XieGetClientData, XieFloExportClientPhoto, XieTecEncodeUncompressedSingle, XieTecEncodeUncompressedTriple, XieTecEncodeG31D, XieTecEncodeG32D, XieTecEncodeG42D, XieTecEncodeServerChoice, XieTecEncodeJPEGBaseline, XieTecEncodeJPEGLossless, XieTecEncodeTIFF2, XieTecEncodeTIFFPackBits

XieFloExportClientROI **XIElib - Photoflo Element Functions**

Name

XieFloExportClientROI - specify an ExportClientROI element and set its parameters

Syntax

```
void XieFloExportClientROI (element, src, notify)
   XiePhotoElement *element;
   XiePhototag src:
   XieExportNotify notify;
```

Arguments

Specifies the XiePhotoElement structure to use. element Specifies the element supplying the list-of-rectangles. srcSpecifies whether to enable sending an ExportAvailable notify

event.

Description

An ExportClientROI element allows a list-of-rectangles, imported using an ImportROI or an ImportClientROI element, to be retrieved by the client. The actual transport of list-of-rectangles data through the protocol stream is requested using a GetClientData element.

One of three standard export notify values can be assigned to *notify*:

xieValDisable xieValFirstData xieValNewData

> If notify was specified as xieValFirstData, this event will be sent only the first time data become available; otherwise, if xieValNewData was specified, this event will be generated each time the amount of data available changes from zero to nonzero.

Structures

XieFloExportClientROI sets the XiePhotoElement structure field elemType to xieElemExportClientROI, which identifies the element as an ExportClientROI. and sets the fields of the member structure ExportClientROI using the arguments in the argument list.

```
typedef unsigned XieExportNotify;
typedef unsigned XiePhototag;
typedef struct {
   int elemType:
   union {
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

 $egin{array}{lll} {
m xieErrNoFloSource} & {
m Invalid} \ src \ {
m xieErrNoFloValue} & {
m Invalid} \ notify \end{array}$

See Also

XieFloImportROI, XieFloImportClientROI, XieGetClientData

XIElib - Photoflo Element Functions XieFloExportDrawable

Name

XieFloExportDrawable - specify an ExportDrawable element and set its parameters

Syntax

```
void XieFloExportDrawable (element, src, drawable, gc, dst_x, dst_y)
   XiePhotoElement *element;
   XiePhototag src;
   Drawable drawable;
   GC gc;
   int dst_x;
   int dst y;
```

Arguments

element	Specifies the XiePhotoElement structure to use.
src	Specifies the element supplying constrained source

data.

drawable Specifies the Window or Pixmap into which the data will

be written.

gc Specifies the GContext to be used when transferring

pixels to *drawable*.

 dst_x Specifies where the data should be placed in drawable. Specifies where the data should be placed in drawable.

Description

An ExportDrawable element allows Colormap index data to be exported to a Window or Pixmap.

The following components are used from *gc*: function, plane-mask, subwindow-mode, clip-x-origin, clip-y-origin, and clip-mask.

The levels of src must exactly match the depth of drawable and gc (that is, levels must be 2depth).

Structures

XieFloExportDrawable sets the XiePhotoElement structure field elemType to xieElemExportDrawable, which identifies the element as an ExportDrawable, and sets the fields of the member structure ExportDrawable using the arguments in the argument list.

typedef unsigned XiePhototag;

```
typedef struct {
   int elemType;
   union {
    ...
    struct {
```

```
XiePhototag src;
Drawable drawable;
GC gc;
int dst_x;
int dst_y;
} ExportDrawable;
...
} data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloDrawable Invalid drawable

xieErrNoFloGC Invalid gc

xieErrNoFloMatch Invalid *src* data: triple band, unconstrained, levels does

not match depth

xieErrNoFloSource Invalid src

See Also

XieFloExportDrawablePlane

Functions

XieFloExportDrawablePlane

Name

XieFloExportDrawablePlane - specify an ExportDrawablePlane element and set its parameters

Syntax

```
void XieFloExportDrawablePlane (element, src, drawable, gc, dst_x, dst_y)
    XiePhotoElement *element;
    XiePhototag src;
    Drawable drawable;
    GC gc;
    int dst_x;
    int dst_y;
```

Arguments

element	Specifies the XiePhotoElement structure to use.
src	Specifies the element supplying constrained bitonal
	source data.
drawable	Specifies the Window or Pixmap into which the data will
	be written.
gc	Specifies the GContext to be used when transferring
	pixels to drawable.
dst x	Specifies where the data should be placed in <i>drawable</i> .
dst_y	Specifies where the data should be placed in <i>drawable</i> .

Description

An ExportDrawablePlane element allows single-band single-bit (bitonal) data to be exported to a Window or a Pixmap.

The following components are used from gc: function, plane-mask, foreground, background, fill-style, subwindow-mode, clip-x-origin, clip-y-origin, and clip-mask. For the fill-style component of gc, values of FillSolid and FillTiled are treated as synonyms for FillOpaqueStippled.

Structures

XieFloExportDrawablePlane sets the XiePhotoElement structure field elemType to xieElemExportDrawablePlane, which identifies the element as an ExportDrawablePlane, and sets the fields of the member structure ExportDrawablePlane using the arguments in the argument list.

typedef unsigned XiePhototag;

```
typedef struct {
   int elemType;
   union {
    ...
    struct {
```

```
XiePhototag src;
Drawable drawable;
GC gc;
int dst_x;
int dst_y;
} ExportDrawablePlane;
...
} data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloDrawable Invalid drawable

xieErrNoFloGC Invalid gc

xieErrNoFloMatch Invalid src data: triple band, not constrained, levels > 2

xieErrNoFloSource Invalid src

See Also

XieFloExportDrawable

Name

XieFloExportLUT - specify an ExportLUT element and set its parameters

Syntax

```
void XieFloExportLUT (element, src, lut, merge, start)
    XiePhotoElement *element;
    XiePhototag src;
    XieLut lut;
    Bool merge;
    XieLTriplet start;
```

Arguments

elementSpecifies the XiePhotoElement structure to use.srcSpecifies the element supplying lookup table data.lutSpecifies the ID of the LUT to receive the data.mergeSpecifies how new array entries replace existing

entries.

start Specifies the index of the first array entry that should

be written in *lut*, per band.

Description

An ExportLUT element allows data imported from an ImportLUT or ImportClientLUT element to be saved in an existing LUT resource.

merge specifies that new array entries from src should replace entries that already exist within lut. If merge is False, start must be zero for each band. In this case, lut will inherit the attributes of src and be populated with its data; the previous attributes and data of lut are overwritten when the photoflo completes. If merge is True and lut has existing attributes, the data from src will replace the data from lut, beginning at position start. If start is True, but start has not yet been populated, it is an error.

The attributes of *src* must match those of *lut*, and the combination of *start* and the length of *src* must specify a valid subrange existing within *lut*.

Structures

XieFloExportLUT sets the XiePhotoElement structure field elemType to xieElemExportLUT, which identifies the element as an ExportLUT, and sets the fields of the member structure ExportLUT using the arguments in the argument list.

```
typedef XID XieLut;
typedef unsigned long XieLTriplet[3];
typedef unsigned XiePhototag;

typedef struct {
   int elemType;
```

```
union {
...
struct {
    XiePhototag src;
    XieLut lut;
    Bool merge;
    XieLTriplet start;
    } ExportLUT;
    ...
} data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory)

xieErrNoFloLUT Invalid lut

xieErrNoFloMatch merge true and attributes do not match between src

and lut, or

merge true and start + src length is not a subrange of

lut

xieErrNoFloSource Invalid src

xieErrNoFloValue merge false and start nonzero

See Also

XieFloImportLUT, XieFloImportClientLUT

XIElib - Photoflo Element Functions XieFloExportPhotomap

Name

XieFloExportPhotomap - specify an ExportPhotomap element and set its parameters

Syntax

void XieFloExportPhotomap (element, src, photomap, encode tech,

encode_param)

XiePhotoElement *element;

XiePhototag src;

XiePhotomap *photomap*;

XieEncodeTechnique encode tech;

XiePointer encode param;

Arguments

elementsrcSpecifies the XiePhotoElement structure to use.Specifies the element supplying source data.

photomap Specifies the ID of the photomap resource to receive the

data.

encode tech Specifies the image compression or formatting

technique.

encode_param Specifies the list of additional parameters required by

encode tech.

Description

An ExportPhotomap element allows data from photoflo operations to be saved in a photomap. A photomap is a server resource that can be used to store image data.

photomap will inherit the attributes of src and be populated with its data. The previous attributes and data of photomap are overwritten when the photoflo completes.

Encode techniques define the techniques that can be used to compress an image or format it as uncompressed data. One of the following standard encode technique values can be assigned to *encode tech*:

xieValEncodeServerChoice xieValEncodeUncompressedSingle xieValEncodeUncompressedTriple xieValEncodeG31D xieValEncodeG32D xieValEncodeG42D xieValEncodeJPEGBaseline xieValEncodeJPEGLossless xieValEncodeTIFF2 xieValEncodeTIFFPackBits If a vendor defined additional private encode techniques, the private technique values given to these techniques can be assigned to *encode tech*.

Structures

XieFloExportPhotomap sets the XiePhotoElement structure field elemType to xieElemExportPhotomap, which identifies the element as an ExportPhotomap, and sets the fields of the member structure ExportPhotomap using the arguments in the argument list.

```
typedef unsigned XiePhototag;
typedef XID XiePhotomap;
typedef unsigned XieEncodeTechnique;
typedef struct {
   int elemType;
   union {
      struct {
          XiePhototag src;
          XiePhotomap photomap;
          XieEncodeTechnique encode tech;
         XiePointer encode param;
      } ExportPhotomap;
   } data;
} XiePhotoElement;
/* Definitions for EncodeTechniques */
#define xieValEncodeServerChoice
                                           1
#define xieValEncodeUncompressedSingle
                                           2
                                           3
#define xieValEncodeUncompressedTriple
#define xieValEncodeG31D
                                           4
                                           6
#define xieValEncodeG32D
#define xieValEncodeG42D
                                           8
#define xieValEncodeJPEGBaseline
                                           10
#define xieValEncodeJPEGLossless
                                           12
#define xieValEncodeTIFF2
                                           14
#define xieValEncodeTIFFPackBits
                                           16
```

Errors

xieErrNoFloAllocInsufficient resources (for example, memory)xieErrNoFloPhotomapInvalid photomapxieErrNoFloSourceInvalid srcxieErrNoFloTechniqueInvalid encode tech or encode param

See Also

XieTecEncodeUncompressedSingle, XieTecEncodeUncompressedTriple, XieTecEncodeG31D, XieTecEncodeG32D, XieTecEncodeG42D, XieTecEncodeServerChoice, XieTecEncodeJPEGBaseline, XieTecEncodeTIFF2, XieTecEncodeTIFFPackBits

Name

XieFloExportROI - specify an ExportROI element and set its parameters

Syntax

```
void XieFloExportROI (element, src, roi)
    XiePhotoElement *element;
    XiePhototag src;
    XieRoi roi;
```

Arguments

element Specifies the XiePhotoElement structure to use.
 src Specifies the element supplying a list-of-rectangles.
 roi Specifies the ID of the ROI resource to receive the data.

Description

An ExportROI element allows data imported from an ImportROI or ImportClientROI element to be saved in an existing Rectangles-Of-Interest (ROI) resource.

roi will be populated with new data. The previous data of roi are overwritten after the photoflo completes.

Structures

XieFloExportROI sets the XiePhotoElement structure field elemType to xieElemExportROI, which identifies the element as an ExportROI, and sets the fields of the member structure ExportROI using the arguments in the argument list.

```
typedef XID XieRoi;
typedef unsigned XiePhototag;

typedef struct {
    int elemType;
    union {
        ...
        struct {
            XiePhototag src;
            XieRoi roi;
        } ExportROI;
        ...
    } data;
} XiePhotoElement;
```

Errors

xieErrNoFloAlloc Insufficient resources (for example, memory) xieErrNoFloROI Invalid *roi*

xieErrNoFloSource Invalid src

See Also

XieFloImportROI, XieFloImportClientROI

Name

XieTecColorAllocAll - allocate and fill an XieColorAllocAllParam structure

Syntax

```
XieColorAllocAllParam *XieTecColorAllocAll (fill) unsigned long fill;
```

Arguments

fill

Specifies the fill value to use for pixels which cannot be allocated.

Returns

The XieColorAllocAllParam structure.

Description

XieTecColorAllocAll allocates and returns a pointer to an XieColorAllocAllParam structure. The returned structure represents the list of parameters required by the AllocAll color allocation technique and may be used as the $color_alloc_param$ argument of XieFloConvertToIndex (when the $color_alloc_tech$ argument is xieValColorAllocAll).

If insufficient memory is available, XieTecColorAllocAll returns NULL. To free the memory allocated to this structure, use XFree.

The *AllocAll* color allocation technique allocates a read-only Colormap cell for each new pixel found. If the Colormap runs out of cells, the remaining new pixels are mapped to *fill*. A ColorAlloc event, which warns the client that results are of lesser fidelity than desired, will be sent if it is necessary to use *fill*, and the client has requested it (see XieFloConvertToIndex). AllocAll is appropriate only for dynamic Colormaps and requires that the number of discrete image pixels fit within the size of the Colormap to avoid running out of cells.

Structures

XieTecColorAllocAll sets the structure field fill to the value of the argument fill.

```
typedef struct {
    unsigned long fill;
} XieColorAllocAllParam;
```

See Also

XieFloConvertToIndex

XIElib - Technique Functions

XieTecColorAllocMatch

Name

XieTecColorAllocMatch - allocate and fill an XieColorAllocMatchParam structure

Syntax

XieColorAllocMatchParam *XieTecColorAllocMatch (match_limit, gray_limit) double match_limit; double gray limit;

Arguments

match_limit Specifies the color allocation control value.
gray limit Specifies the gray scale allocation control value.

Returns

The XieColorAllocMatchParam structure.

Description

XieTecColorAllocMatch allocates and returns a pointer to an XieColorAllocMatchParam structure. The returned structure represents the list of parameters required by the AllocMatch color allocation technique and may be used as the $color_alloc_param$ argument of XieFloConvertToIndex (when the $color_alloc_tech$ argument is xieValColorAllocMatch).

If insufficient memory is available, XieTecColorAllocMatch returns NULL. To free the memory allocated to this structure, use XFree.

The AllocMatch color allocation technique allows a trade-off between image fidelity and Colormap usage via a pair of granularity parameters. The highest priority is given to allocating read-only cells in a sequence that provides an even distribution of pixels throughout the colorspace. Secondary priority is given to the frequency of usage of image pixels. Any image pixel that is a close enough match to an existing read-only cell will share that cell (where "close" is determined by the granularity controls). For other image pixels, new read-only allocations are made. When no more cells are available, each remaining image pixel is matched to the closest read-only cell. The AllocMatch color allocation technique is appropriate for both static and dynamic Colormaps. For the sake of computational efficiency the number of discrete image pixels should not exceed the size of the Colormap.

match_limit and gray_match control the allocation of colors and gray shades, respectively. The minimum value (0.0) specifies exact matches (within the limits of the Colormap). The maximum value (1.0) encompasses the entire colorspace within which no new cells are allocated. A ColorAlloc event, which warns the client that results are of lesser fidelity than desired, can be sent if the Colormap runs out of cells.

Structures

XieTecColorAllocMatch sets the structure field match_limit to the value of the argument *match_limit*; and the structure field gray_limit to the value of the argument *gray_limit*.

```
typedef struct {
    float match_limit;
    float gray_limit;
} XieColorAllocMatchParam;
```

See Also

 $\it XieFloConvertToIndex$

XIElib - Technique Functions XieTecColorAllocRequantize

Name

 $\label{locate} \mbox{XieTecColorAllocRequantize-allocate and fill an XieColorAllocRequantizeParam} \\ \mbox{structure}$

Syntax

XieColorAllocRequantizeParam *XieTecColorAllocRequantize (max_cells) unsigned long max cells;

Arguments

max cells

Specifies the maximum number of Colormap allocations to allow.

Returns

The XieColorAllocRequantizeParam structure.

Description

XieTecColorAllocRequantize allocates and returns a pointer to an XieColorAllocRequantizeParam structure. The returned structure represents the list of parameters required by the AllocRequantize color allocation technique and may be used as the *color_alloc_param* argument of XieFloConvertToIndex (when the *color_alloc tech* argument is xieValColorAllocRequantize).

If insufficient memory is available, XieTecColorAllocRequantize returns NULL. To free the memory allocated to this structure, use XFree.

The AllocRequantize color allocation technique first reduces the total number of discrete pixel values in the image to be no more than a specified number and then allocates the resulting pixel values as read-only cells from the Colormap. One method of accomplishing this reduction process can be found in "Color image quantization for frame buffer display" (Heckbert, P. S., *Comput. Graph.* 16, 3).

If max_cells is zero or greater than the number of unallocated Colormap cells, the reduction algorithm will restrict its output to the number of free cells. A ColorAlloc event, which warns the client that results are of lesser fidelity than desired, can be sent if the number of pixels had to be restricted to a lesser number than max_cells because of a lack of free Colormap cells. The AllocRequantize color allocation technique is appropriate only for dynamic Colormaps.

Structures

XieTecColorAllocRequantize sets the structure field \max_{cells} to the value of the argument \max_{cells} .

```
typedef struct {
    unsigned long max_cells;
} XieColorAllocRequantizeParam;
```

See Also

XieFloConvertToIndex

XieTecRGBToCIELab

Name

XieTecRGBToCIELab - allocate and fill an XieRGBToCIELabParam structure

Syntax

XieRGBToCIELabParam *XieTecRGBToCIELab (matrix, white_adjust_tech, white_adjust_param)

XieMatrix *matrix*;

XieWhiteAdjustTechnique white adjust tech;

XiePointer white_adjust_param;

Arguments

matrix Specifies the conversion matrix.

white_adjust_tech Specifies the WhiteAdjust technique to be used. Specifies the list of parameters required by

white adjust tech.

Returns

The XieRGBToCIELabParam structure.

Description

XieTecRGBToCIELab allocates and returns a pointer to an XieRGBToCIELabParam structure. The returned structure represents the list of parameters required by the RGBToCIELab color conversion technique and may be used as the *color_param* argument of XieFloConvertFromRGB (when the *color space* argument is xieValRGBToCIELab).

If insufficient memory is available, XieTecRGBToCIELab returns NULL. To free the memory allocated to this structure, use XFree.

XieTecRGBToCIELab converts RGB data to the CIELab colorspace, an international standard designed for perceptual uniformity. The colorspace coordinates are denoted by L, a, and b and are defined in CIE, Recommendations on Uniform Color Spaces, Color-Difference Equations, Psychometric Color Terms (Bureau Central de la CIE [Supplement 2 of CIE Publication 15 (E-1.3.1) 1971], 1978).

matrix is a 3x3 RGB-to-CIEXYZ conversion matrix (the source white point is also encoded in matrix). white_adjust_tech is the WhiteAdjust technique that can be used to shift the white point of the output data. white_adjust_param is the list of parameters required by white adjust tech.

The input data type can be constrained or unconstrained; the output data type is always unconstrained. When the input is constrained, the data are normalized to the range [0, 1] (that is, scaled by 1/(levels - 1) prior to the conversion).

WhiteAdjust techniques define the white point adjustment techniques that can be used when converting to or from the RGB colorspace. One of the following standard WhiteAdjust technique values can be assigned to *white adjust tech*:

```
xieValWhiteAdjustNone
xieValWhiteAdjustCIELabShift
```

If a vendor defined additional private WhiteAdjust techniques, the private technique values given to these techniques can be assigned to <code>white_adjust_tech</code>.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecRGBToCIELab sets the structure field matrix to the values of the argument *matrix*; the structure field white_adjust_tech to the value of the argument *white_adjust_tech*; and the structure field white_adjust_param to the value of the argument *white adjust param*.

```
typedef float XieMatrix[9];
typedef unsigned XieWhiteAdjustTechnique;
typedef struct {
    XieMatrix matrix;
    XieWhiteAdjustTechnique white_adjust_tech;
    XiePointer white_adjust_param;
} XieRGBToCIELabParam;

/* Definitions for WhiteAdjust Techniques */
#define xieValWhiteAdjustDefault 0
#define xieValWhiteAdjustNone 1
#define xieValWhiteAdjustCIELabShift 2
```

See Also

XieFloConvertFromRGB, XieTecWhiteAdjustCIELabShift

XieTecRGBToCIEXYZ

XIElib - Technique Functions

Name

XieTecRGBToCIEXYZ - allocate and fill an XieRGBToCIEXYZParam structure

Syntax

XieRGBToCIEXYZParam *XieTecRGBToCIEXYZ (matrix, white_adjust_tech, white adjust param)

XieMatrix *matrix*;

XieWhiteAdjustTechnique white adjust tech;

XiePointer white_adjust_param;

Arguments

matrix Specifies the conversion matrix.

white adjust tech Specifies the WhiteAdjust technique to be used. Specifies the list of parameters required by

white adjust tech.

Returns

The XieRGBToCIEXYZParam structure.

Description

XieTecRGBToCIEXYZ allocates and returns a pointer to an XieRGBToCIEXYZParam structure. The returned structure represents the list of parameters required by the RGBToCIEXYZ color conversion technique and may be used as the *color_param* argument of XieFloConvertFromRGB (when the *color_space* argument is xieValRGBToCIEXYZ).

If insufficient memory is available, XieTecRGBToCIEXYZ returns NULL. To free the memory allocated to this structure, use XFree.

XieTecRGBToCIEXYZ converts RGB data to the CIEXYZ colorspace, an international standard device-independent colorspace.

matrix is a 3x3 RGB-to-CIEXYZ conversion matrix (the source white point is also encoded in matrix). white_adjust_tech is the WhiteAdjust technique that can be used to shift the white point of the output data. white_adjust_param is the list of parameters required by white_adjust_tech.

The input data type can be constrained or unconstrained; the output data type is always unconstrained. When the input is constrained, the data are normalized to the range [0, 1] (that is, scaled by 1/(levels - 1) prior to the conversion).

WhiteAdjust techniques define the white point adjustment techniques that can be used when converting to or from the RGB colorspace. One of the following standard WhiteAdjust technique values can be assigned to *white_adjust_tech*:

xieValWhiteAdjustDefault xieValWhiteAdjustNone xieValWhiteAdjustCIELabShift If a vendor defined additional private WhiteAdjust techniques, the private technique values given to these techniques can be assigned to white adjust tech.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecRGBToCIEXYZ sets the structure field matrix to the values of the argument *matrix*; the structure field white_adjust_tech to the value of the argument *white_adjust_tech*; and the structure field white_adjust_param to the value of the argument *white_adjust_param*.

```
typedef float XieMatrix[9];
typedef unsigned XieWhiteAdjustTechnique;
typedef struct {
    XieMatrix matrix;
    XieWhiteAdjustTechnique white_adjust_tech;
    XiePointer white_adjust_param;
} XieRGBToCIEXYZParam;

/* Definitions for WhiteAdjust Techniques */
#define xieValWhiteAdjustDefault 0
#define xieValWhiteAdjustNone 1
#define xieValWhiteAdjustCIELabShift 2
```

See Also

XieFloConvertFromRGB, XieTecWhiteAdjustCIELabShift

XieConstant bias:

Name

XieTecRGBToYCbCr - allocate and fill an XieRGBToYCbCrParam structure

Syntax

```
XieRGBToYCbCrParam *XieTecRGBToYCbCr (levels, luma_red, luma_green, luma_blue, bias)

XieLevels levels;
double luma_red;
double luma_green;
double luma blue;
```

Arguments

levels Specifies the output levels.

luma_redSpecifies the proportion of red in the luminance band.luma_greenSpecifies the proportion of green in the luminance band.luma_blueSpecifies the proportion of blue in the luminance band.biasSpecifies an offset to add to the output pixels values.

Returns

The XieRGBToYCbCrParam structure.

Description

XieTecRGBToYCbCr allocates and returns a pointer to an XieRGBToYCbCrParam structure. The returned structure represents the list of parameters required by the RGBToYCbCr color conversion technique and may be used as the *color_param* argument of XieFloConvertFromRGB (when the *color_space* argument is xieValRGBToYCbCr).

If insufficient memory is available, XieTecRGBToYCbCr returns NULL. To free the memory allocated to this structure, use XFree.

XieTecRGBToYCbCr converts RGB data to the YCbCr colorspace. Source data may be constrained or unconstrained; the output type will match. If the source data is constrained, *levels* determines the output levels; otherwise *levels* is ignored.

Structures

XieTecRGBToYCbCr sets the structure field levels to the values of the argument *levels*; the structure fields luma_red, luma_green, luma_blue to the values of the arguments *luma_red*, *luma_green*, *luma_blue*; and the structure field bias to the values of the argument *bias*.

```
typedef float XieConstant[3];
typedef unsigned long XieLevels[3];
typedef struct {
    XieLevels levels;
    float luma_red;
    float luma_green;
    float luma blue;
```

XieConstant bias; } XieRGBToYCbCrParam;

See Also

 $\it XieFloConvertFromRGB$

Name

XieTecRGBToYCC - allocate and fill an XieRGBToYCCParam structure

Syntax

XieRGBToYCCParam *XieTecRGBToYCC (levels, luma_red, luma_green, luma_blue, scale)

XieLevels levels; double luma_red; double luma_green; double luma_blue; double scale;

Arguments

levels Specifies the output levels.

luma_redSpecifies the proportion of red in the luminance band.luma_greenSpecifies the proportion of green in the luminance band.luma_blueSpecifies the proportion of blue in the luminance band.scaleSpecifies a compression factor to apply to the output

pixels values.

Returns

The XieRGBToYCCParam structure.

Description

XieTecRGBToYCC allocates and returns a pointer to an XieRGBToYCCParam structure. The returned structure represents the list of parameters required by the RGBToYCC color conversion technique and may be used as the *color_param* argument of XieFloConvertFromRGB (when the *color_space* argument is xieValRGBToYCC).

If insufficient memory is available, XieTecRGBToYCC returns NULL. To free the memory allocated to this structure, use XFree.

XieTecRGBToYCC converts RGB data to the YCC colorspace. The PhotoYCC color-encoding scheme is defined in: KODAK PhotoCD System - A Planning Guide for Developers (Eastman Kodak Co., Part no. DCI200R, 1991).

Source data may be constrained or unconstrained; the output type will match. If the source data is constrained, *levels* determines the output levels; otherwise *levels* is ignored. Typical values cited in the literature for *scale* are in the range of about 1.35 to 1.4.

Structures

XieTecRGBToYCC sets the structure field levels to the values of the argument *levels*; the structure fields luma_red, luma_green, luma_blue are set to the values of the arguments *luma_red*, *luma_green*, *luma_blue*; and the structure field scale to the value of the argument *scale*.

```
typedef unsigned long XieLevels[3];
typedef struct {
```

```
XieLevels levels;
float luma_red;
float luma_green;
float luma_blue;
float scale;
} XieRGBToYCCParam;
```

See Also

XieFloConvertFromRGB

XIElib - Technique Functions

XieTecCIELabToRGB

Name

XieTecCIELabToRGB - allocate and fill an XieCIELabToRGBParam structure

Syntax

XieCIELabToRGBParam *XieTecCIELabToRGB (matrix, white_adjust_tech, white adjust param, gamut tech, gamut param)

XieMatrix *matrix*;

XieWhiteAdjustTechnique white adjust tech;

XiePointer white_adjust_param;

XieGamutTechnique gamut_tech;

XiePointer gamut_param;

Arguments

matrix Specifies the conversion matrix.

white_adjust_tech Specifies the WhiteAdjust technique to be used. Specifies the list of parameters required by

white adjust tech.

gamut tech Specifies the Gamut technique to be used.

gamut_param Specifies the list of parameters required by gamut_tech.

Returns

The XieCIELabToRGBParam structure.

Description

XieTecCIELabToRGB allocates and returns a pointer to an XieCIELabToRGBParam structure. The returned structure represents the list of parameters required by the CIELabToRGB color conversion technique and may be used as the *color_param* argument of XieFloConvertToRGB (when the *color space* argument is xieValCIELabToRGB).

If insufficient memory is available, XieTecCIELabToRGB returns NULL. To free the memory allocated to this structure, use XFree.

XieTecCIELabToRGB converts CIELab data to the RGB colorspace. The CIELab colorspace is an international standard designed for perceptual uniformity. The colorspace coordinates are denoted by L, a, and b and are defined in CIE, Recommendations on Uniform Color Spaces, Color-Difference Equations, Psychometric Color Terms (Bureau Central de la CIE [Supplement 2 of CIE Publication 15 (E-1.3.1) 1971], 1978).

matrix is a 3x3 CIEXYZ-to-RGB conversion matrix (the target white point is also encoded in matrix). white_adjust_tech is the WhiteAdjust technique that can be used to shift the white point of the source data prior to conversion. white_adjust_param is the list of parameters required by white_adjust_tech. gamut_tech is the Gamut technique that can be used to keep the output pixels within the bounds of the RGB colorspace. gamut_param is the list of parameters required by gamut_tech.

The input data type must be unconstrained; the output data type is also unconstrained.

WhiteAdjust techniques define the white point adjustment techniques that can be used when converting to or from the RGB colorspace. One of the following standard WhiteAdjust technique values can be assigned to *white adjust tech*:

xieValWhiteAdjustDefault xieValWhiteAdjustNone xieValWhiteAdjustCIELabShift

If a vendor defined additional private WhiteAdjust techniques, the private technique values given to these techniques can be assigned to white adjust tech.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Gamut techniques define the gamut compression techniques used to deal with converted colors that lie outside the gamut of the RGB space. One of the following standard gamut technique values can be assigned to *gamut tech*:

xieValGamutDefault xieValGamutNone xieValGamutClipRGB

If a vendor defined additional private gamut techniques, the private technique values given to these techniques can be assigned to *gamut tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecCIELabToRGB sets the structure field matrix to the values of the argument *matrix*; the structure field white_adjust_tech to the value of the argument *white_adjust_tech*; the structure field white_adjust_param to the value of the argument *white_adjust_param*; the structure field gamut_tech to the value of the argument *gamut_tech*; and the structure field gamut_param to the value of the argument *gamut_param*.

```
typedef float XieMatrix[9];
typedef unsigned XieGamutTechnique;
typedef unsigned XieWhiteAdjustTechnique;
typedef struct {
   XieMatrix matrix:
   XieWhiteAdjustTechnique white adjust tech;
   XiePointer white adjust param;
   XieGamutTechnique gamut tech;
   XiePointer gamut param;
} XieCIELabToRGBParam;
/* Definitions for WhiteAdjust Techniques */
#define xieValWhiteAdjustDefault
                                            0
#define xieValWhiteAdjustNone
                                            1
#define xieValWhiteAdjustCIELabShift
                                            2
/* Definitions for Gamut Techniques */
```

#define xieValGamutDefault	0
#define xieValGamutNone	1
#define xieValGamutClipRGB	2

See Also

Xie Flo Convert To RGB, Xie Tec White Adjust CIELab Shift

XieTecCIEXYZToRGB

XIElib - Technique Functions

Name

XieTecCIEXYZToRGB - allocate and fill an XieCIEXYZToRGBParam structure

Syntax

XieCIEXYZToRGBParam *XieTecCIEXYZToRGB (matrix, white_adjust_tech, white adjust param, gamut tech, gamut param)

XieMatrix *matrix*;

XieWhiteAdjustTechnique white adjust tech;

XiePointer white_adjust_param;

XieGamutTechnique gamut_tech;

XiePointer gamut_param;

Arguments

matrix Specifies the conversion matrix.

white_adjust_tech Specifies the WhiteAdjust technique to be used. Specifies the list of parameters required by

white adjust tech.

gamut tech Specifies the Gamut technique to be used.

gamut_param Specifies the list of parameters required by gamut_tech.

Returns

The XieCIEXYZToRGBParam structure.

Description

XieTecCIEXYZToRGB allocates and returns a pointer to an XieCIEXYZToRGBParam structure. The returned structure represents the list of parameters required by the CIEXYZToRGB color conversion technique and may be used as the *color_param* argument of XieFloConvertToRGB (when the *color space* argument is xieValCIEXYZToRGB).

If insufficient memory is available, XieTecCIEXYZToRGB returns NULL. To free the memory allocated to this structure, use XFree.

XieTecCIEXYZToRGB converts CIEXYZ data to the RGB colorspace. The CIEXYZ colorspace is an international standard device-independent colorspace.

matrix is a 3x3 CIEXYZ-to-RGB conversion matrix (the target white point is also encoded in matrix). white_adjust_tech is the WhiteAdjust technique that can be used to shift the white point of the source data prior to conversion. white_adjust_param is the list of parameters required by white_adjust_tech. gamut_tech is the Gamut technique that can be used to keep the output pixels within the bounds of the RGB colorspace. gamut_param is the list of parameters required by gamut_tech.

The input data type must be unconstrained; the output data type is also unconstrained.

WhiteAdjust techniques define the white point adjustment techniques that can be used when converting to or from the RGB colorspace. One of the following standard WhiteAdjust technique values can be assigned to *white_adjust_tech*:

xieValWhiteAdjustDefault xieValWhiteAdjustNone xieValWhiteAdjustCIELabShift

If a vendor defined additional private WhiteAdjust techniques, the private technique values given to these techniques can be assigned to white adjust tech.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Gamut techniques define the gamut compression techniques used to deal with converted colors that lie outside the gamut of the RGB space. One of the following standard gamut technique values can be assigned to *gamut tech*:

xieValGamutDefault xieValGamutNone xieValGamutClipRGB

If a vendor defined additional private gamut techniques, the private technique values given to these techniques can be assigned to *gamut tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecCIEXYZToRGB sets the structure field matrix to the values of the argument *matrix*; the structure field white_adjust_tech to the value of the argument *white_adjust_tech*; the structure field white_adjust_param to the value of the argument *white_adjust_param*; the structure field gamut_tech to the value of the argument *gamut_tech*; and the structure field gamut_param to the value of the argument *gamut_param*.

```
typedef float XieMatrix[9];
typedef unsigned XieGamutTechnique;
typedef unsigned XieWhiteAdjustTechnique;
typedef struct {
   XieMatrix matrix;
   XieWhiteAdjustTechnique white adjust tech;
   XiePointer white adjust param;
   XieGamutTechnique gamut tech;
   XiePointer gamut param;
} XieCIEXYZToRGBParam;
/* Definitions for WhiteAdjust Techniques */
#define xieValWhiteAdjustDefault
                                           0
#define xieValWhiteAdjustNone
                                           1
#define xieValWhiteAdjustCIELabShift
                                           2
/* Definitions for Gamut Techniques */
#define xieValGamutDefault
                                           0
                                           1
#define xieValGamutNone
#define xieValGamutClipRGB
                                           2
```

See Also

Xie Flo Convert To RGB, Xie Tec White Adjust CIELab Shift

Name

XieTecYCbCrToRGB - allocate and fill an XieYCbCrToRGBParam structure

Syntax

XieYCbCrToRGBParam *XieTecYCbCrToRGB (levels, luma_red, luma_green, luma_blue, bias, gamut_tech, gamut_param)

XieLevels levels; double luma_red; double luma_green; double luma_blue; XieConstant bias; XieGamutTechnique gamut_tech;

XiePointer *gamut param*;

Arguments

levels Specifies the output levels.

luma red Specifies the proportion of red in the luminance band

(Y).

luma green Specifies the proportion of green in the luminance band

(Y).

luma blue Specifies the proportion of blue in the luminance band

(Y).

bias Specifies an offset to remove from the source pixels

values.

aamut tech Specifies the Gamut technique to be used.

gamut param Specifies the list of parameters required by gamut tech.

Returns

The XieYCbCrToRGBParam structure.

Description

XieTecYCbCrToRGB allocates and returns a pointer to an XieYCbCrToRGBParam structure. The returned structure represents the list of parameters required by the YCbCrToRGB color conversion technique and may be used as the *color_param* argument of XieFloConvertToRGB (when the *color_space* argument is xieValYCbCrToRGB).

If insufficient memory is available, XieTecYCbCrToRGB returns NULL. To free the memory allocated to this structure, use XFree.

XieTecYCbCrToRGB converts YCbCr data to the RGB colorspace. Source data may be constrained or unconstrained; the output type will match. If the source data is constrained, *levels* determines the output levels; otherwise *levels* is ignored.

Gamut techniques define the gamut compression techniques used to deal with converted colors that lie outside the gamut of the RGB space. One of the following standard gamut technique values can be assigned to *gamut tech*:

xieValGamutNone xieValGamutClipRGB

If a vendor defined additional private gamut techniques, the private technique values given to these techniques can be assigned to *gamut tech*.

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecYCbCrToRGB sets the structure field levels to the values of the argument *levels*; the structure fields luma_red, luma_green, luma_blue to the values of the arguments *luma_red*, *luma_green*, *luma_blue*; the structure field bias to the values of the argument *bias*; the structure field gamut_tech to the value of the argument *gamut_tech*; and the structure field gamut_param to the value of the argument *gamut_param*.

```
typedef float XieConstant[3];
typedef unsigned long XieLevels[3];
typedef unsigned XieGamutTechnique;
typedef struct {
   XieLevels levels:
   float luma red;
   float luma_green; float luma_blue;
   XieConstant bias:
   XieGamutTechnique gamut tech;
   XiePointer gamut param;
} XieYCbCrToRGBParam;
/* Definitions for Gamut Techniques */
#define xieValGamutDefault
                                              0
#define xieValGamutNone
                                              1
#define xieValGamutClipRGB
                                              2
```

See Also

XieFloConvertToRGB

XieTecYCCToRGB

XIElib - Technique Functions

Name

XieTecYCCToRGB - allocate and fill an XieYCCToRGBParam structure

Syntax

XieYCCToRGBParam *XieTecYCCToRGB (levels, luma_red, luma_green, luma_blue, scale, gamut_tech, gamut_param)

XieLevels levels; double luma_red; double luma_green; double luma_blue; double scale;

XieGamutTechnique gamut_tech;

XiePointer gamut param;

Arguments

levels Specifies the output levels.

luma red Specifies the proportion of red in the luminance band

(Y).

luma green Specifies the proportion of green in the luminance band

(Y).

luma blue Specifies the proportion of blue in the luminance band

(Y).

scale Specifies an expansion factor to apply to the output

pixels values.

aamut tech Specifies the Gamut technique to be used.

gamut param Specifies the list of parameters required by gamut tech.

Returns

The XieYCCToRGBParam structure.

Description

XieTecYCCToRGB allocates and returns a pointer to an XieYCCToRGBParam structure. The returned structure represents the list of parameters required by the YCCToRGB color conversion technique and may be used as the *color_param* argument of XieFloConvertToRGB (when the *color_space* argument is xieValYCCToRGB).

If insufficient memory is available, XieTecYCCToRGB returns NULL. To free the memory allocated to this structure, use XFree.

XieTecYCCToRGB converts YCC data to the RGB colorspace. The PhotoYCC color-encoding scheme is defined in KODAK PhotoCD System - A Planning Guide for Developers (Eastman Kodak Co., Part no. DCI200R, 1991).

Source data may be constrained or unconstrained; the output type will match. If the source data is constrained, *levels* determines the output levels; otherwise *levels* is ignored. Typical values cited in the literature for *scale* are in the range of about 1.35 to 1.4.

Gamut techniques define the gamut compression techniques used to deal with converted colors that lie outside the gamut of the RGB space. One of the following standard gamut technique values can be assigned to *gamut tech*:

```
xieValGamutDefault
xieValGamutNone
xieValGamutClipRGB
```

If a vendor defined additional private gamut techniques, the private technique values given to these techniques can be assigned to *gamut tech* .

The server is required to support the default technique that is bound to one of the standard techniques defined or a private technique.

Structures

XieTecYCCToRGB sets the structure field levels to the values of the argument *levels*; the structure fields luma_red, luma_green, luma_blue to the values of the arguments *luma_red*, *luma_green*, *luma_blue*; the structure field scale to the values of the argument *scale*; the structure field gamut_tech to the value of the argument *gamut_tech*; and the structure field gamut_param to the value of the argument *gamut_param*.

```
typedef unsigned long XieLevels[3];
typedef unsigned XieGamutTechnique:
typedef struct {
   XieLevels levels:
   float luma red;
   float luma green;
   float luma blue;
   float scale;
   XieGamutTechnique gamut tech;
   XiePointer gamut param;
} XieYCCToRGBParam;
/* Definitions for Gamut Techniques */
#define xieValGamutDefault
                                            0
#define xieValGamutNone
                                            1
                                            2
#define xieValGamutClipRGB
```

See Also

XieFloConvertToRGB

Name

XieTecClipScale - allocate and fill an XieClipScaleParam structure

Syntax

```
XieClipScaleParam *XieTecClipScale (in_low, in_high, out_low, out_high)
    XieConstant in_low;
    XieConstant in_high;
    XieLTriplet out_low;
    XieLTriplet out_high;
```

Arguments

in_low	Specifies an input pixel limit.
in_high	Specifies an input pixel limit.
out low	Specifies an output pixel limit.
out_high	Specifies an output pixel limit.

Returns

The XieClipScaleParam structure.

Description

XieTecClipScale allocates and returns a pointer to an XieClipScaleParam structure. The returned structure represents the list of parameters required by the constrain technique and may be used as the *constrain_param* argument of XieFloConstrain (when the *constrain_tech* argument is xieValClipScale).

If insufficient memory is available, XieTecClipScale returns NULL. To free the memory allocated to this structure, use XFree.

For each band, output pixels will be clipped to the range [out_low , out_high]. If in_low is less than in_high , then all pixels less than or equal to in_low will map to out_low , and all pixels that are greater than or equal to in_high will map to out_high . All intermediate pixel values are scaled proportionately to the output range. Nonintegral output values are rounded to the nearest integer.

If in_low is greater than in_high , then all pixels that are greater than or equal to in_low will map to out_low , and all pixels that are less than or equal to in_high will map to out_high . All intermediate pixel values will be linearly mapped to the output range, such that in_low maps to out_low , and in_high maps to out_high . Nonintegral output values are rounded to the nearest integer.

 in_low should not equal in_high , out_low should be less than out_high , and out_high should not exceed levels - 1.

Structures

XieTecClipScale sets the structure fields input_low, input_high to the values of the arguments *in_low*, *in_high*; and the structure fields output_low, output_high to the values of the arguments *out low*, *out high*.

```
typedef float XieConstant[3];
typedef unsigned long XieLTriplet[3];
typedef struct {
    XieConstant input_low,input_high;
    XieLTriplet output_low,output_high;
} XieClipScaleParam;
```

See Also

XieFloConstrain

XIElib - Technique Functions

XieTecConvolveConstant

Name

 $\label{lem:convolveConstant} \mbox{XieTecConvolveConstantParam structure} \\$

Syntax

XieConvolveConstantParam *XieTecConvolveConstant (constant) XieConstant constant;

Arguments

constant

Specifies the value to use if pixels are required from beyond the edge of the image.

Returns

The XieConvolveConstantParam structure.

Description

XieTecConvolveConstant allocates and returns a pointer to an XieConvolveConstantParam structure. The returned structure represents the list of parameters required by the convolve technique and may be used as the <code>convolve_param</code> argument of XieFloConvolve (when the <code>convolve_tech</code> argument is xieValConvolveConstant).

If insufficient memory is available, XieTecConvolveConstant returns NULL. To free the memory allocated to this structure, use XFree.

Various methods of handling edge conditions are provided for convolve techniques. These techniques determine what pixel values are used when the convolve technique requires data beyond the image bounds. Convolve techniques come into play only when the kernel is positioned partially off the edge of the image. Data around the edges of a *process domain* are convolved with adjacent image pixels wherever possible. A *process domain* is inserted in many element definitions and is used to restrict the element's processing to a subset of the source data pixels; it can be either a list-of-rectangles or a control-plane.

The Constant Convolve technique uses the value specified by *constant* if pixels are required from beyond the edge of the image.

Structures

XieTecConvolveConstant sets the structure field constant to the value of the argument *constant*.

```
typedef float XieConstant[3];
typedef struct {
    XieConstant constant;
} XieConvolveConstantParam;
```

See Also

XieFloConvolve

Functions

XieTecDecodeUncompressedSingle

Name

XieTecDecodeUncompressedSingle - allocate and fill an XieDecodeUncompressedSingleParam structure

Syntax

 $\label{lem:code_uncompressed_single} Xie Decode Uncompressed Single \\ \textit{(fill_order, pixel_order, pixel_stride, left_pad, scanline_pad)}$

XieOrientation fill_order; XieOrientation pixel_order; unsigned int pixel_stride; unsigned int left_pad; unsigned int scanline pad;

Arguments

fill order Specifies the method of pixel packing.

pixel order Specifies pixel ordering within the data stream.

pixel stride Specifies the number of bits between consecutive pixels

within a scanline.

left_padscanline padSpecifies the number of pad bits in each scanline.Specifies a multiple of bytes to which each scanline is

padded.

Returns

The XieDecodeUncompressedSingleParam structure.

Description

XieTecDecodeUncompressedSingle allocates and returns a pointer to an XieDecodeUncompressedSingleParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the $decode_param$ argument of XieFloImportClientPhoto (when the $decode_tech$ argument is xieValDecodeUncompressedSingle).

If insufficient memory is available, XieTecDecodeUncompressedSingle returns NULL. To free the memory allocated to this structure, use XFree.

The decode uncompressed single technique is used when no compression scheme has been applied to single band image data. The parameters define the format of the data stream of uncompressed data (the server may reformat the data as it chooses prior to processing or storage). When multiple pixels are put in the same byte, or a pixel spans multiple bytes, $fill_order$ specifies whether the pixels (or parts of pixels) are packed into the most or least significant bits of a byte first. For pixels that span a byte boundary, $pixel_order$ defines whether the most or least significant bits of the pixel are transported first within the data stream. One of the following standard orientation values can be assigned to $fill_order$ and $pixel_order$:

xieValLSFirst xieValMSFirst

The following table shows the relationship between *fill_order* and *pixel_order*, using two 10-bit pixels, each with two bits of pad (within each pixel the LS-bits are "0" and "a", the MS-bits are "9" and "j", the pad bits are "p").

fill order	LSFirst (pixel order)	MSFirst (pixel order)
LSFirst	76543210 dcbapp98	98765432 jihgpp10
	ppjihgfe	ppfedcba
MSFirst	76543210 98ppdcba	98765432 10ppjihg
	jihgfepp	fedcbapp

pixel_stride is the number of bits between the start of consecutive pixels within a scanline; it must be at least enough bits to contain the number of input levels. left_pad is the number of pad bits preceding the first image pixel in each scanline; if the server's Alignment attribute is Alignable, or pixel_stride fits the definition of Alignable, the value of left_pad must be a multiple of pixel_stride or a multiple of 8; otherwise, left_pad may be any arbitrary value. scanline_pad defines a multiple of bytes to which each scanline is padded; valid values are: 0 (not aligned), 1, 2, 4, 8, and 16. The total number of bits-per-scanline in the data stream includes: left_pad, the image data (width x pixel_stride), and sufficient additional bits to satisfy scanline_pad.

Structures

XieTecDecodeUncompressedSingle sets the structure field fill_order to the value of the argument fill_order; the structure field pixel_order to the value of the argument pixel_order; the structure field pixel_stride to the value of the argument pixel_stride; the structure field left_pad to the value of the argument left_pad; and the structure field scanline_pad to the value of the argument scanline pad.

```
typedef unsigned XieOrientation;
typedef struct {
    XieOrientation fill_order;
    XieOrientation pixel_order;
    unsigned int pixel_stride;
    unsigned int left_pad;
    unsigned int scanline_pad;
} XieDecodeUncompressedSingleParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloImportClientPhoto, XiePutClientData

Functions

XieTecDecodeUncompressedTriple

Name

XieTecDecodeUncompressedTriple - allocate and fill an XieDecodeUncompressedTripleParam structure

Syntax

XieDecodeUncompressedTripleParam *XieTecDecodeUncompressedTriple (fill_order, pixel_order, band_order, interleave, pixel_stride, left_pad, scanline_pad)

XieOrientation fill_order; XieOrientation pixel_order; XieOrientation band_order; XieInterleave interleave; unsigned char pixel_stride[3]; unsigned char left_pad[3]; unsigned char scanline_pad[3];

Arguments

fill_order Specifies the method of pixel packing.

pixel_order Specifies pixel ordering within the data stream.

band order Specifies the order of the image data sent through the

protocol stream.

interleave Specifies how the image bands are interleaved.

pixel stride Specifies the number of bits between consecutive pixels

within a scanline.

left_padSpecifies the number of pad bits in each scanline.scanline_padSpecifies a multiple of bytes to which each scanline is

padded.

Returns

The XieDecodeUncompressedTripleParam structure.

Description

XieTecDecodeUncompressedTriple allocates and returns a pointer to an XieDecodeUncompressedTripleParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the <code>decode_param</code> argument of XieFloImportClientPhoto (when the <code>decode_tech</code> argument is xieValDecodeUncompressedTriple).

If insufficient memory is available, $XieTecDecodeUncompressedTriple\ returns\ NULL$. To free the memory allocated to this structure, use XFree.

The decode uncompressed triple technique is used when no compression scheme has been applied to triple band image data. The parameters define the format of the data stream of uncompressed data (the server may reformat the data as it chooses prior to processing or storage). When multiple pixels are put in the same byte, or a pixel spans multiple bytes, *fill_order* specifies whether the pixels (or parts of pixels) are packed into the most or least significant bits of a byte first. For pixels that span a byte boundary, *pixel_order* defines whether the most or least significant bits of the pixel are transported first within the data stream.

One of the following standard orientation values can be assigned to *fill_order* and *pixel order*:

xieValLSFirst xieValMSFirst

The following table shows the relationship between *fill_order* and *pixel_order*, using two 10-bit pixels, each with two bits of pad (within each pixel the LS-bits are "0" and "a", the MS-bits are "9" and "j", the pad bits are "p")

fill order	LSFirst (pixel order)	MSFirst (pixel order)
LSFirst	76543210 dcbapp98 ppjihgfe	98765432 jihgpp10 ppfedcba
MSFirst	76543210 98ppdcba jihgfepp	98765432 10ppjihg fedcbapp

pixel_stride is the number of bits between the start of consecutive pixels within a scanline; It must be at least enough bits to contain the number of input levels. left_pad is the number of pad bits preceding the first image pixel in each scanline; if the server's Alignment attribute is Alignable, or pixel_stride fits the definition of Alignable, the value of left_pad must be a multiple of pixel_stride or a multiple of 8; otherwise, left_pad may be any arbitrary value. scanline_pad defines a multiple of bytes to which each scanline is padded; valid values are: 0 (not aligned), 1, 2, 4, 8, and 16. The total number of bits-per-scanline in the data stream includes: left_pad, the image data (width x pixel_stride), and sufficient additional bits to satisfy scanline_pad.

interleave describes how the image bands are interleaved (per pixel within a single plane, or sent as three separate planes); if interleave is xieValBandByPixel, inter-band dimensions must match: the widths and the heights of all bands must match. One of the following standard interleave values can be assigned to interleave:

xieValBandByPixel xieValBandByPlane

band_order is the order of the image bands or image planes as they are transmitted through the protocol stream. band_order can be set to one of the standard orientation values. The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace : red is the least significant band of RGB data. For band-by-pixel data, band_order specifies whether this band is put in the least or most significant bits of a pixel:

LSFirst	MSFirst
$B_1B_0G_2G_1G_0R_2R_1R_0$	$R_2R_1R_0G_2G_1G_0B_1B_0$

For band-by-plane data, *band_order* specifies whether this band corresponds with the least significant or most significant image plane. Each plane is transported as a separate data stream:

	band	LSFirst	MSFirst
Γ	0	R7R6 R5R4 R3R2R1R0	B7B6B5B4B3B2B1B0

1	G7 G6G5G4G3G2 G1G0	G7 G6G 5G 4G 3G2 G1G 0
2	B7B6B5B4B3B2B1B0	R7R6 R5R4 R3R2R1R0

Structures

XieTecDecodeUncompressedTriple sets the structure field fill_order to the value of the argument fill_order; the structure field pixel_order to the value of the argument pixel_order; the structure field band_order to the value of the argument band_order; the structure field interleave to the value of the argument interleave; the structure field pixel_stride to the value of the argument pixel_stride; the structure field left_pad to the value of the argument left_pad; and the structure field scanline pad to the value of the argument scanline pad.

```
typedef unsigned XieOrientation;
typedef unsigned XieInterleave;
typedef struct {
   unsigned char left pad[3];
   XieOrientation fill order:
   unsigned char pixel stride[3];
   XieOrientation pixel order;
   unsigned char scanline pad[3];
   XieOrientation band order;
   XieInterleave interleave:
} XieDecodeUncompressedTripleParam;
/* Definitions of Orientation Types */
#define xieValLSFirst
                                              1
#define xieValMSFirst
                                             2
/* Definitions for Interleave */
#define xieValBandBvPixel
#define xieValBandByPlane
```

See Also

XieFloImportClientPhoto, XiePutClientData

XieTecDecodeG31D

XIElib - Technique Functions

Name

XieTecDecodeG31D - allocate and fill an XieDecodeG31DParam structure

Syntax

XieDecodeG31DParam *XieTecDecodeG31D (encoded_order, normal,

radiometric)

XieOrientation encoded order;

Bool normal;

Bool radiometric;

Arguments

encoded order Specifies the bit order of the encoded data.

normal Specifies how the data was processed when it was

originally encoded.

radiometric Specifies how "white runs" are decoded.

Returns

The XieDecodeG31DParam structure.

Description

XieTecDecodeG31D allocates and returns a pointer to an XieDecodeG31DParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the *decode_param* argument of XieFloImportClientPhoto (when the *decode_tech* argument is xieValDecodeG31D).

If insufficient memory is available, XieTecDecodeG31D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G31D is the CCITT group 3 one-dimensional encoding technique as defined by CCITT T.4, "Standardization of Group 3 Facsimile Apparatus for Document Transmission".

encoded_order specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to encoded_order:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

radiometric specifies that "white runs" in the encoded data should be represented as image ones upon decode (maximum intensity), or conversely, they will be decoded as image zeros if radiometric is False. normal specifies that

the data was processed according to its normal fill-order when it was originally encoded.

Structures

XieTecDecodeG31D sets the structure field encoded_order to the value of the argument <code>encoded_order</code>; the structure field normal to the value of the argument <code>normal</code>; and the structure field radiometric to the value of the argument <code>radiometric</code>.

See Also

XieFloImportClientPhoto, XiePutClientData

XieTecDecodeG32D

XIElib - Technique Functions

Name

XieTecDecodeG32D - allocate and fill an XieDecodeG32DParam structure

Syntax

XieDecodeG32DParam *XieTecDecodeG32D (encoded_order, normal,

radiometric)

XieOrientation encoded order;

Bool normal;

Bool radiometric;

Arguments

encoded order Specifies the bit order of the encoded data.

normal Specifies how the data was processed when it was

originally encoded.

radiometric Specifies how "white runs" are decoded.

Returns

The XieDecodeG32DParam structure.

Description

XieTecDecodeG32D allocates and returns a pointer to an XieDecodeG32DParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the *decode_param* argument of XieFloImportClientPhoto (when the *decode_tech* argument is xieValDecodeG32D).

If insufficient memory is available, XieTecDecodeG32D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G32D is the CCITT group 3 two-dimensional encoding technique as defined by CCITT T.4, "Standardization of Group 3 Facsimile Apparatus for Document Transmission".

encoded_order specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to encoded_order:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

radiometric specifies that "white runs" in the encoded data should be represented as image ones upon decode (maximum intensity), or conversely, they will be decoded as image zeros if radiometric is False. normal specifies that

the data was processed according to its normal fill-order when it was originally encoded.

Structures

XieTecDecodeG32D sets the structure field encoded_order to the value of the argument <code>encoded_order</code>; the structure field normal to the value of the argument <code>normal</code>; and the structure field radiometric to the value of the argument <code>radiometric</code>.

See Also

XieFloImportClientPhoto, XiePutClientData

XieTecDecodeG42D

XIElib - Technique Functions

Name

XieTecDecodeG42D - allocate and fill an XieDecodeG42DParam structure

Syntax

 $XieDecodeG42DParam\ *XieTecDecodeG42D\ (encoded_order,\ normal,\

radiometric))

XieOrientation encoded order;

Bool normal;

Bool radiometric;

Arguments

encoded order Specifies the bit order of the encoded data.

normal Specifies how the data was processed when it was

originally encoded.

radiometric Specifies how "white runs" are decoded.

Returns

The XieDecodeG42DParam structure.

Description

XieTecDecodeG42D allocates and returns a pointer to an XieDecodeG42DParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the *decode_param* argument of XieFloImportClientPhoto (when the *decode_tech* argument is xieValDecodeG42D).

If insufficient memory is available, XieTecDecodeG42D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G42D is the CCITT group 4 two-dimensional encoding technique as defined by CCITT T.6, "Facsimile Coding Schemes and Coding Control Functions for Group 4 Facsimile Apparatus".

encoded_order specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to encoded_order:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

radiometric specifies that "white runs" in the encoded data should be represented as image ones upon decode (maximum intensity), or conversely, they will be decoded as image zeros if radiometric is False. normal specifies that

the data was processed according to its normal fill-order when it was originally encoded.

Structures

XieTecDecodeG42D sets the structure field encoded_order to the value of the argument <code>encoded_order</code>; the structure field normal to the value of the argument <code>normal</code>; and the structure field radiometric to the value of the argument <code>radiometric</code>.

See Also

XieFloImportClientPhoto, XiePutClientData

XieTecDecodeTIFF2

XIElib - Technique Functions

Name

XieTecDecodeTIFF2 - allocate and fill an XieDecodeTIFF2Param structure

Syntax

XieDecodeTIFF2Param *XieTecDecodeTIFF2 (encoded_order, normal,

radiometric)

XieOrientation encoded order;

Bool *normal*;

Bool radiometric;

Arguments

encoded order Specifies the bit order of the encoded data.

normal Specifies how the data was processed when it was

originally encoded.

radiometric Specifies how "white runs" are decoded.

Returns

The XieDecodeTIFF2Param structure.

Description

XieTecDecodeTIFF2 allocates and returns a pointer to an XieDecodeTIFF2Param structure. The returned structure represents the list of parameters required by the decode technique and may be used as the *decode_param* argument of XieFloImportClientPhoto (when the *decode_tech* argument is xieValDecodeTIFF2).

If insufficient memory is available, XieTecDecodeTIFF2 returns NULL. To free the memory allocated to this structure, use XFree.

TIFF-2 is modified Huffman encoding as described in "TIFF Tag Image File Format", revision 6.0, draft 2, by Aldus Corporation (TIFF compression scheme 2).

encoded_order specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to encoded_order:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

radiometric specifies that "white runs" in the encoded data should be represented as image ones upon decode (maximum intensity), or conversely, they will be decoded as image zeros if radiometric is False. normal specifies that

the data was processed according to its normal fill-order when it was originally encoded.

Structures

XieTecDecodeTIFF2 sets the structure field encoded_order to the value of the argument <code>encoded_order</code>; the structure field normal to the value of the argument <code>normal</code>; and the structure field radiometric to the value of the argument <code>radiometric</code>.

```
typedef unsigned XieOrientation;
typedef struct {
    XieOrientation encoded_order;
    Bool normal;
    Bool radiometric;
} XieDecodeTIFF2Param;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloImportClientPhoto, XiePutClientData

XIElib - Technique Functions XieTecDecodeTIFFPackBits

Name

 $\label{lem:condet} \mbox{XieTecDecodeTIFFPackBits-allocate and fill an XieDecodeTIFFPackBitsParam structure}$

Syntax

XieDecodeTIFFPackBitsParam *XieTecDecodeTIFFPackBits (encoded_order, normal)

XieOrientation encoded order;

Bool normal:

Arguments

encoded order Specifies the bit order of the encoded data.

normal Specifies how the data was processed when it was

originally encoded.

Returns

The XieDecodeTIFFPackBitsParam structure.

Description

XieTecDecodeTIFFPackBits allocates and returns a pointer to an XieDecodeTIFFPackBitsParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the <code>decode_param</code> argument of XieFloImportClientPhoto (when the <code>decode_tech</code> argument is xieValDecodeTIFFPackBits).

If insufficient memory is available, XieTecDecodeTIFFPackBits returns NULL. To free the memory allocated to this structure, use XFree.

TIFF-PackBits is byte-oriented run-length encoding as described in "TIFF Tag Image File Format", revision 6.0, draft 2, by Aldus Corporation (TIFF compression scheme 32773).

<code>encoded_order</code> specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to <code>encoded order</code>:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

normal specifies that the data was processed according to its normal fill-order when it was originally encoded.

Structures

XieTecDecodeTIFFPackBits sets the structure field encoded_order to the value of the argument <code>encoded_order</code> and the structure field normal to the value of the argument <code>normal</code>.

```
typedef unsigned XieOrientation;
typedef struct {
    XieOrientation encoded_order;
    Bool normal;
} XieDecodeTIFFPackBitsParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

 $\it XieFloImportClientPhoto, XiePutClientData$

XIElib - Technique Functions XieTecDecodeJPEGBaseline

Name

XieTecDecodeJPEGBaseline - allocate and fill an XieDecodeJPEGBaselineParam structure

Syntax

Xie Decode JPEGBaseline Param~*Xie Tec Decode JPEGBaseline~(interleave, and also become a support of the property of the pro

band order, up sample)

XieInterleave *interleave*; XieOrientation *band order*;

Bool up sample;

Arguments

interleave Specifies how the image bands will be interleaved. band order Specifies the order in which the image bands were

originally encoded.

up sample Specifies how interleaved encoded data are up-sampled.

Returns

The XieTecDecodeJPEGBaselineParam structure.

Description

XieDecodeJPEGBaseline allocates and returns a pointer to an XieDecodeJPEGBaselineParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the $decode_param$ argument of XieFloImportClientPhoto (when the $decode_tech$ argument is xieValDecodeJPEGBaseline).

If insufficient memory is available, XieTecDecodeJPEGBaseline returns NULL. To free the memory allocated to this structure, use XFree.

The JPEG baseline technique is the baseline Huffman DCT encoding technique that is defined in ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images". Only JPEG Interchange Format (JIF) is supported: all tables, compressed data, and so on are embedded in the data stream, all delineated by markers.

interleave determines whether all bands of a triple band image will be interleaved within a single encoded stream or whether three separate encoded streams will be supplied. One of the following standard interleave values can be assigned to interleave:

xieValBandByPixel xieValBandByPlane

For triple band data, *band_order* specifies the order in which the image bands were originally encoded. One of the following standard orientation values can be assigned to *band order*:

xieValLSFirst xieValMSFirst The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: red is the least significant band of RGB data. band_order specifies whether this band corresponds with the least significant or most significant image plane. Each plane is decoded into a separate data stream:

band	LSFirst	MSFirst
0	Red band	Blue band
1	Green band	Green band
2	Blue band	Red band

up_sample specifies that if any bands in an interleaved encoded data stream are down-sampled, they should be up-sampled by the JPEG decoder.

The arguments *interleave*, *band_order*, and *up_sample* are ignored for single band images, and *up_sample* is always ignored if *interleave* is band-by-plane. If *up_sample* is False and some of the encoded bands of an interleaved image were down-sampled, an alternative method for up-sampling the image would be to use a geometry element with appropriate *band_mask* and *sample* technique parameters.

Structures

XieTecDecodeJPEGBaseline sets the structure field interleave to the value of the argument *interleave*; the structure field band_order to the value of the argument *band_order*; and the structure field up_sample to the value of the argument *up sample*.

```
typedef unsigned XieOrientation;
typedef struct {
   XieInterleave interleave:
   XieOrientation band order:
   Bool up sample;
} XieDecodeJPEGBaselineParam;
/* Definitions for Interleave */
#define xieValBandByPixel
                                             1
#define xieValBandByPlane
                                             2
/* Definitions of Orientation Types */
#define xieValLSFirst
                                             1
#define xieValMSFirst
                                             2
```

See Also

XieFloImportClientPhoto, XieFloConvertToRGB, XieTecYCbCrToRGB, XiePutClientData

XIElib - Technique Functions XieTecDecodeJPEGLossless

Name

XieTecDecodeJPEGLossless - allocate and fill an XieDecodeJPEGLosslessParam structure

Syntax

XieDecodeJPEGLosslessParam *XieTecDecodeJPEGLossless (interleave,

band order)

XieInterleave interleave:

XieOrientation band_order;

Arguments

interleave Specifies how the image bands will be interleaved. Specifies the order in which the image bands were

originally encoded.

Returns

 $The \ Xie Decode JPEGLossless Param\ structure.$

Description

XieTecDecodeJPEGLossless allocates and returns a pointer to an XieDecodeJPEGLosslessParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the <code>decode_param</code> argument of XieFloImportClientPhoto (when the <code>decode_tech</code> argument is xieValDecodeJPEGLossless).

If insufficient memory is available, XieTecDecodeJPEGLossless returns NULL. To free the memory allocated to this structure, use XFree.

The JPEG lossless technique is the Huffman predictive sequential lossless encoding technique that is defined in ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images".

This technique is not available in the R6 sample implementation of XIE.

interleave describes how the bands of triple band data are interleaved; either all bands are interleaved within a single encoded stream, or three separate encoded streams are expected. One of the following standard interleave values can be assigned to *interleave*:

xieValBandByPixel xieValBandByPlane

For triple band data, *band_order* specifies the order in which the image bands were originally encoded. One of the following standard orientation values can be assigned to *band order*:

xieValLSFirst xieValMSFirst

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: red is the least significant band of RGB data.

band_order specifies whether this band corresponds with the least significant or most significant image plane. Each plane is decoded into a separate data stream:

band	LSFirst	MSFirst
0	Red band	Blue band
1	Green band	Green band
2	Blue band	Red band

The arguments interleave and band order are ignored for single band images.

Structures

XieTecDecodeJPEGLossless sets the structure field interleave to the value of the argument *interleave*; and the structure field band_order to the value of the argument *band order*.

```
typedef unsigned XieOrientation;
typedef struct {
    XieInterleave interleave;
    XieOrientation band_order;
} XieDecodeJPEGLosslessParam;
/* Definitions for Interleave */
#define xieValBandByPixel 1
#define xieValBandByPlane 2

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloImportClientPhoto, XiePutClientData

XieTecDitherOrdered

Name

XieTecDitherOrdered - allocate and fill an XieDitherOrderedParam structure

Syntax

XieDitherOrderedParam *XieTecDitherOrdered (threshold_order) unsigned int threshold order;

Arguments

threshold_order Specifies a value to determine the size of the dither

matrix.

Returns

The XieDitherOrderedParam structure.

Description

XieTecDitherOrdered allocates and returns a pointer to an XieDitherOrderedParam structure. The returned structure represents the list of parameters required by the decode technique and may be used as the <code>decode_param</code> argument of XieFloImportClientPhoto (when the <code>decode_tech</code> argument is xieValDitherOrdered).

If insufficient memory is available, XieTecDitherOrdered returns NULL. To free the memory allocated to this structure, use XFree.

The dispersed-dot ordered dither technique replaces a matrix, or block, of pixels with a patterned matrix of pixels. This patterned matrix of pixels is applied across the entire image. Because these patterns may introduce artifacts that are distracting to the eye, the $threshold_order$ parameter is available to determine the size of the dither matrix, and therefore, the number of levels that can be simulated. If the value of $threshold_order$ is m, the threshold matrix can simulate 2m + 1 levels.

Structures

XieTecDitherOrdered sets the structure field threshold_order to the value of the argument *threshold_order*.

```
typedef struct {
    unsigned int threshold_order;
} XieDitherOrderedParam;
```

See Also

XieFloDither

XIElib - Technique

Functions

XieTecEncodeUncompressedSingle

Name

XieTecEncodeUncompressedSingle - allocate and fill an XieEncodeUncompressedSingleParam structure

Syntax

XieEncodeUncompressedSingleParam *XieTecEncodeUncompressedSingle (fill order, pixel order, pixel stride, scanline pad)

XieOrientation fill_order; XieOrientation pixel_order; unsigned int pixel_stride; unsigned int scanline pad;

Arguments

fill_order Specifies the method of pixel packing.

pixel order Specifies pixel ordering within the data stream.

pixel stride Specifies the number of bits between consecutive pixels

within a scanline.

scanline pad Specifies a multiple of bytes to which each scanline is

padded.

Returns

The XieEncodeUncompressedSingleParam structure.

Description

XieTecEncodeUncompressedSingle allocates and returns a pointer to an XieEncodeUncompressedSingleParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeUncompressedSingle).

If insufficient memory is available, XieTecEncodeUncompressedSingle returns NULL. To free the memory allocated to this structure, use XFree.

The encode uncompressed single technique is used when no compression scheme is to be applied to single band image data. The parameters define the format of the data stream of uncompressed data that is made available for client retrieval via XieGetClientData. When multiple pixels are put in the same byte or a pixel spans multiple bytes, $fill_order$ specifies whether the pixels (or parts of pixels) are packed into the most or least significant bits of a byte first. For pixels that span a byte boundary, $pixel_order$ defines whether the most or least significant bits of the pixel are put first within the data stream.

One of the following standard orientation values can be assigned to *fill_order* and *pixel_order*:

xieValLSFirst xieValMSFirst

The following table shows the relationship between *fill_order* and *pixel_order*, using two 10-bit pixels, each with two bits of pad (within each pixel the LS-bits are "0" and "a", the MS-bits are "9" and "j", and the pad bits are "p").

fill order	LSFirst (pixel order)	MSFirst (pixel order)
LSFirst	76543210 dcbapp98 ppjihgfe	98765432 jihgpp10 ppfedcba
MSFirst	76543210 98ppdcba jihgfepp	98765432 10ppjihg fedcbapp

pixel_stride is the number of bits between the start of consecutive pixels within a scanline. It must be at least enough bits to contain the number of source levels. *scanline_pad* defines a multiple of bytes to which each scanline is padded; valid values are: 0 (not aligned), 1, 2, 4, 8, and 16.

Structures

XieTecEncodeUncompressedSingle sets the structure field fill_order to the value of the argument fill_order; the structure field pixel_order to the value of the argument pixel_order; the structure field pixel_stride to the value of the argument pixel_stride; and the structure field scanline_pad to the value of the argument scanline_pad.

```
typedef struct {
    XieOrientation fill_order;
    XieOrientation pixel_order;
    unsigned int pixel_stride;
    unsigned int scanline_pad;
} XieEncodeUncompressedSingleParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

typedef unsigned XieOrientation;

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

Functions

XieTecEncodeUncompressedTriple

Name

XieTecEncodeUncompressedTriple - allocate and fill an XieEncodeUncompressedTripleParam structure

Syntax

XieEncodeUncompressedTripleParam *XieTecEncodeUncompressedTriple (fill_order, pixel_order, band_order, interleave, pixel_stride, scanline pad)

XieOrientation fill_order; XieOrientation pixel_order; XieOrientation band_order; XieInterleave interleave; unsigned char pixel_stride[3]; unsigned char scanline pad[3];

Arguments

fill order Specifies the method of pixel packing.

pixel order Specifies pixel ordering within the data stream.

band_order Specifies the order of the image data sent through the

protocol stream.

interleave Specifies how the image bands are interleaved.

pixel stride Specifies the number of bits between consecutive pixels

within a scanline.

scanline pad Specifies a multiple of bytes to which each scanline is

padded.

Returns

The XieEncodeUncompressedTripleParam structure.

Description

XieTecEncodeUncompressedTriple allocates and returns a pointer to an XieEncodeUncompressedTripleParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeUncompressedTriple).

If insufficient memory is available, XieTecEncodeUncompressedTriple returns NULL. To free the memory allocated to this structure, use XFree.

The encode uncompressed triple technique is used when no compression scheme is to be applied to triple band image data. The parameters define the format of the data stream of uncompressed data that is made available for client retrieval via XieGetClientData. When multiple pixels are put in the same byte or a pixel spans multiple bytes, *fill_order* specifies whether the pixels (or parts of pixels) are packed into the most or least significant bits of a byte first. For pixels that span a byte boundary, *pixel_order* defines whether the most or least significant bits of the pixel are put first within the data stream.

One of the following standard orientation values can be assigned to *fill_order* and *pixel order*:

xieValLSFirst xieValMSFirst

The following table shows the relationship between *fill_order* and *pixel_order*, using two 10-bit pixels, each with two bits of pad (within each pixel the LS-bits are "0" and "a", the MS-bits are "9" and "j", and the pad bits are "p")

fill order	LSFirst (pixel order)	MSFirst (pixel order)
LSFirst	76543210 dcbapp98 ppjihgfe	98765432 jihgpp10 ppfedcba
MSFirst	76543210 98ppdcba jihgfepp	98765432 10ppjihg fedcbapp

pixel_stride is the number of bits between the start of consecutive pixels within a scanline. It must be at least enough bits to contain the number of source levels. scanline_pad defines a multiple of bytes to which each scanline is padded; valid values are: 0 (not aligned), 1, 2, 4, 8, and 16. band_order is the order of the image bands or image planes as they are transmitted through the protocol stream. One of the following standard orientation values can be assigned to band order:

xieValLSFirst xieValMSFirst

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: red is the least significant band of RGB data. For band-by-pixel data, *band_order* specifies whether this band is put in the least or most significant bits of a pixel:

LSFirst	MSFirst
$B_1B_0G_2G_1G_0R_2R_1R_0$	$R_2R_1R_0G_2G_1G_0B_1B_0$

For band-by-plane data, *band_order* specifies whether this band corresponds with the least significant or most significant image plane. Each plane is transported as a separate data stream:

band	LSFirst	MSFirst
0	$R_7R_6R_5R_4R_3R_2R_1R_0$	B7B6B5B4B3B2B1B0
1	G7 G6G 5G4G3G2 G1G0	G7 G6G5G4G3G2 G1G0
2	B7B6B5B4B3B2B1B0	R7R6 R5R4 R3R2R1R0

interleave describes how the bands are interleaved (per pixel within a single plane, or sent as three separate planes). One of the following standard interleave values can be assigned to *interleave*:

xieValBandByPixel xieValBandByPlane

Export of down-sampled band-by-pixel data is not supported: all bands must have equal widths and equal heights.

Structures

XieTecEncodeUncompressedTriple sets the structure field fill_order to the value of the argument fill_order; the structure field pixel_order to the value of the argument pixel_order; the structure field band_order to the value of the argument band_order; the structure field interleave to the value of the argument interleave; the structure field pixel_stride to the value of the argument pixel_stride; and the structure field scanline_pad to the value of the argument scanline_pad.

```
typedef unsigned XieOrientation;
typedef struct {
   unsigned char pixel stride[3];
   XieOrientation pixel order;
   unsigned char scanline pad[3];
   XieOrientation fill order;
   XieOrientation band order:
   XieInterleave interleave:
} XieEncodeUncompressedTripleParam;
/* Definitions of Orientation Types */
#define xieValLSFirst
                                             1
#define xieValMSFirst
                                             2
/* Definitions for Interleave */
#define xieValBandByPixel
                                             1
#define xieValBandByPlane
                                             2
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

XieTecEncodeG31D

XIElib - Technique Functions

Name

XieTecEncodeG31D - allocate and fill an XieEncodeG31DParam structure

Syntax

XieEncodeG31DParam *XieTecEncodeG31D (align_eol, radiometric, encoded order)

Bool align_eol; Bool radiometric;

XieOrientation encoded order;

Arguments

align_eol Specifies the use of fill bits preceding EOL codes.

radiometric Specifies how "white runs" are encoded. encoded order Specifies the bit order of the encoded data.

Returns

The XieEncodeG31DParam structure.

Description

XieTecEncodeG31D allocates and returns a pointer to an XieEncodeG31DParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeG31D).

If insufficient memory is available, XieTecEncodeG31D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G31D is the CCITT group 3 one-dimensional encoding technique as defined by CCITT T.4, "Standardization of Group 3 Facsimile Apparatus for Document Transmission".

If True, $align_eol$, specifies that sufficient fill bits must precede EOL codes to guarantee that each EOL will end on a byte boundary (thus EOL will be a nibble of zero followed by a byte of one: xxxx,0000 $_2$ 0000,0001 $_2$). radiometric specifies that image ones will be encoded as "white runs", or conversely, image zeros will be encoded as "white runs", if radiometric is False. $encoded_order$ specifies the bit order for the encoded data. One of the following standard orientation values can be assigned to $encoded_order$:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

Structures

XieTecEncodeG31D sets the structure field align_eol to the value of the argument <code>align_eol</code>; the structure field radiometric to the value of the argument <code>radiometric</code>; and the structure field encoded_order to the value of the argument <code>encoded_order</code>.

```
typedef unsigned XieOrientation;
typedef struct {
    Bool align_eol;
    Bool radiometric;
    XieOrientation encoded_order;
} XieEncodeG31DParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

Name

XieTecEncodeG32D - allocate and fill an XieEncodeG32DParam structure

Syntax

XieEncodeG32DParam *XieTecEncodeG32D (uncompressed, align_eol, radiometric, encoded order, k factor)

Bool uncompressed; Bool align_eol; Bool radiometric; XieOrientation encoded_order; unsigned long k factor;

Arguments

uncompressed Specifies the use of the uncompressed-mode CCITT

extension.

align eol Specifies the use of fill bits preceding EOL codes.

radiometric Specifies how "white runs" are encoded. encoded order Specifies the bit order of the encoded data.

k factor Specifies the number of two-dimensional scanlines to

produce for each one-dimensional scanline.

Returns

The XieEncodeG32DParam structure.

Description

XieTecEncodeG32D allocates and returns a pointer to an XieEncodeG32DParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the *encode_param* argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the *encode_tech* argument is xieValEncodeG32D).

If insufficient memory is available, XieTecEncodeG32D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G32D is the CCITT group 3 two-dimensional encoding technique as defined by CCITT T.4, "Standardization of Group 3 Facsimile Apparatus for Document Transmission".

If True, *uncompressed*, will enable the use of the uncompressed-mode CCITT extension. If True, *align_eol*, specifies that sufficient fill bits must precede EOL codes to guarantee that each EOL will end on a byte boundary (thus EOL will be a nibble of zero followed by a byte of one: xxxx,00002 0000,00012). *radiometric* specifies that image ones will be encoded as "white runs", or conversely, image zeros will be encoded as "white runs", if *radiometric* is False. *encoded_order* specifies the bit order for the encoded data. One of the following standard orientation values can be assigned to *encoded order*:

xieValLSFirst xieValMSFirst The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

k *factor* specifies the number of two-dimensional scanlines to produce for each one-dimensional scanline.

Structures

XieTecEncodeG32D sets the structure field uncompressed to the value of the argument *uncompressed*; the structure field align_eol to the value of the argument *align_eol*; the structure field radiometric to the value of the argument *radiometric*; the structure field encoded_order to the value of the argument *encoded_order*; and the structure field k_factor to the value of the argument *k factor*.

```
typedef unsigned XieOrientation;
typedef struct {
    Bool uncompressed;
    Bool align_eol;
    Bool radiometric;
    XieOrientation encoded_order;
    unsigned long k_factor;
} XieEncodeG32DParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

XieTecEncodeG42D

XIElib - Technique Functions

Name

XieTecEncodeG42D - allocate and fill an XieEncodeG42DParam structure

Syntax

XieEncodeG42DParam *XieTecEncodeG42D (uncompressed, radiometric, encoded order)

Bool uncompressed;

Bool radiometric;

XieOrientation encoded_order;

Arguments

uncompressed Specifies the use of the uncompressed-mode CCITT

extension.

radiometric Specifies how "white runs" are encoded. encoded_order Specifies the bit order of the encoded data.

Returns

The XieEncodeG42DParam structure.

Description

XieTecEncodeG42D allocates and returns a pointer to an XieEncodeG42DParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeG42D).

If insufficient memory is available, XieTecEncodeG42D returns NULL. To free the memory allocated to this structure, use XFree.

CCITT-G42D is the CCITT group 4 two-dimensional encoding technique as defined by CCITT T.6, "Facsimile Coding Schemes and Coding Control Functions for Group 4 Facsimile Apparatus".

If True, *uncompressed* will enable the use of the uncompressed-mode CCITT extension. *radiometric* specifies that image ones will be encoded as "white runs", or conversely, image zeros will be encoded as "white runs", if *radiometric* is False. *encoded_order* specifies the bit order for the encoded data. One of the following standard orientation values can be assigned to *encoded order*:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

Structures

XieTecEncodeG42D sets the structure field uncompressed to the value of the argument *uncompressed*; the structure field radiometric to the value of the argument *radiometric*; and the structure field encoded_order to the value of the argument *encoded order*.

```
typedef unsigned XieOrientation;
typedef struct {
    Bool uncompressed;
    Bool radiometric;
    XieOrientation encoded_order;
} XieEncodeG42DParam;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

XIElib - Technique Functions XieTecEncodeServerChoice

Name

XieTecEncodeServerChoice - allocate and fill an XieEncodeServerChoiceParam structure

Syntax

XieEncodeServerChoiceParam *XieTecEncodeServerChoice (preference) unsigned int preference;

Arguments

preference

Specifies a "hint" to help the server make its choice.

Returns

The XieEncodeServerChoiceParam structure.

Description

XieTecEncodeServerChoice allocates and returns a pointer to an XieEncodeServerChoiceParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeServerChoice).

If insufficient memory is available, XieTecEncodeServerChoice returns NULL. To free the memory allocated to this structure, use XFree.

The server choice technique allows the server to choose an encode technique when exporting to a photomap. A photomap is a server resource that can be used to store image data. *preference* specifies an optional "hint" that can be provided to help the server make its choice, but the server is not obligated to obey the hint. One of the following standard server choice preference values can be assigned to *preference*:

xieValPreferDefault xieValPreferSpace xieValPreferTime

xieValPreferTime hints that retrieval performance is the desired metric, whereas xieValPreferSpace indicates that frugal use of storage space is more important. Normally the server choice technique must choose a lossless encode technique, but when data is received from an adjacent upstream import element, it may choose to pass the import element's input data directly to the photomap.

Structures

 ${\tt Xie Tec Encode Server Choice \ sets \ the \ structure \ field \ preference \ to \ the \ value \ of \ the \ argument \ preference \ .}$

```
typedef struct {
    unsigned int preference;
} XieEncodeServerChoiceParam;
/* Definitions for ServerChoice Preference Hints */
```

#define xieValPreferDefault	0
#define xieValPreferSpace	1
#define xieValPreferTime	2

See Also

XieFloExportPhotomap

XIElib - Technique Functions XieTecEncodeJPEGBaseline

Name

XieTecEncodeJPEGBaseline - allocate and fill an XieEncodeJPEGBaselineParam structure

Syntax

XieEncodeIPEGBaselineParam *XieTecEncodeIPEGBaseline (interleave, band order, horizontal samples, vertical samples, a table, a size, ac table, ac size, dc table, dc size) XieInterleave interleave: XieOrientation band order; unsigned char horizontal samples[3]; unsigned char vertical samples[3]: char*q table; unsigned int q size; char *ac table: unsigned int ac size; char *dc table; unsigned int dc size;

Arguments

interleave Specifies how the image bands will be interleaved. band order Specifies the order in which the image bands were

originally encoded.

Specifies the horizontal sampling factor. horizontal samples vertical samples Specifies the vertical sampling factor. *q* table Specifies the quantization table.

Specifies the number of elements in *q table*. q size

Specifies the AC Huffman table. ac table

Specifies the number of elements in ac table. ac size

dc table Specifies the DC Huffman table.

dc size Specifies the number of elements in *dc table*.

Returns

The XieEncodeJPEGBaselineParam structure.

Description

XieTecEncode[PEGBaseline allocates and returns a pointer to an XieEncodeJPEGBaselineParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the encode param argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the encode tech argument is xieValEncodeJPEGBaseline).

If insufficient memory is available, XieTecEncodeJPEGBaseline returns NULL. XieTecEncodeIPEGBaseline allocates memory for the structure fields q table, ac table, and dc table; to free the memory allocated to the structure XieEncodeJPEGBaselineParam, use XieFreeEncodeJPEGBaseline.

JPEG-Baseline is baseline Huffman DCT encoding as defined by ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images". A stream of

JPEG Interchange Format (JIF) data is produced: all tables, compressed data, and so on are embedded in the data stream, all delineated by markers.

For optimal results, clients should ensure that the colorspace of triple band image data flowing into ExportClientPhoto or ExportPhotomap, for encoding by the JPEGBaseline encoder, is YCbCr.

interleave determines whether all bands of a triple band image will be interleaved within a single encoded stream or whether three separate encoded streams will be produced. One of the following standard interleave values can be assigned to *interleave*:

xieValBandByPixel xieValBandByPlane

For triple band data, *band_order* specifies the order in which the image bands were originally encoded. One of the following standard orientation values can be assigned to *band order*:

xieValLSFirst xieValMSFirst

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: red is the least significant band of RGB data. <code>band_order</code> specifies whether this band corresponds with the least significant or most significant image plane. Each plane is encoded from a separate data stream:

band	LSFirst	MSFirst
0	Red band	Blue band
1	Green band	Green band
2	Blue band	Red band

The arguments *horizontal_samples* and *vertical_samples* are the horizontal and vertical sampling factors. *q_table* is the quantization table. *ac_table* specifies the AC Huffman table and *dc_table* specifies the DC Huffman table.

There may be one q_table per band or a single q_table shared between all bands. Generally there is a single AC/DC pair of Huffman tables, but for triple band band-by-pixel data there may be two pairs of tables (one for the luminance band and the other for the chromanance bands). If any table is specified with zero length, it indicates that the server implementor is to supply that table (for example, the example tables defined in ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images").

The arguments interleave, band_order, horizontal_samples, and vertical_samples are ignored for single band images, and horizontal_samples and vertical_samples are always ignored if interleave is band-by-plane. horizontal_samples and vertical_samples and vertical_samples share the definitions and restrictions stipulated for parameters Hi and Vi, respectively, that are specified in annexes A and B of ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images".

Structures

XieTecEncodeJPEGBaseline sets the structure field interleave to the value of the argument *interleave*; the structure field band_order to the value of the argument *band_order*; the structure field horizontal_sample to the values of the argument *horizontal_sample*; the structure field vertical_sample to the values of the argument *vertical_sample*; and the structure fields q_table, q_size, ac_table, ac_size, dc_table, dc_size to the values of the arguments q_table, q_size, ac_table, ac_size, dc_table, dc_size.

```
typedef unsigned XieOrientation;
typedef struct {
   XieInterleave interleave:
   XieOrientation band order:
   unsigned char horizontal samples[3];
   unsigned char vertical samples[3];
   char *q table;
   unsigned int q size;
   char *ac table;
   unsigned int ac size;
   char *dc table;
   unsigned int dc size;
} XieEncodeIPEGBaselineParam;
/* Definitions for Interleave */
#define xieValBandByPixel
                                              1
#define xieValBandByPlane
                                              2
/* Definitions of Orientation Types */
#define xieValLSFirst
                                              1
#define xieValMSFirst
                                              2.
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieFreeEncodeJPEGBaseline, XieFloConvertFromRGB, XieTecRGBToYCbCr, XieGetClientData

XIElib - Technique Functions XieTecEncodeJPEGLossless

Name

XieTecEncodeJPEGLossless - allocate and fill an XieEncodeJPEGLosslessParam structure

Syntax

XieEncodeJPEGLosslessParam *XieTecEncodeJPEGLossless (interleave, band order, predictor, table, table size)

XieInterleave interleave; XieOrientation band_order; unsigned char predictor[3]; char *table; unsigned int table size;

Arguments

interleave Specifies how the image bands will be interleaved. Specifies the order in which the image bands were

originally encoded.

predictor Specifies the predictor selection value.

table Specifies the lossless entropy encoding table. table size Specifies the number of elements in table.

Returns

The XieEncodeJPEGLosslessParam structure.

Description

XieTecEncodeJPEGLossless allocates and returns a pointer to an XieEncodeJPEGLosslessParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeJPEGLossless).

If insufficient memory is available, XieTecEncodeJPEGLossless returns NULL. XieTecEncodeJPEGLossless allocates memory for the structure field table; to free the memory allocated to the structure XieEncodeJPEGLosslessParam, use XieFreeEncodeJPEGLossless.

JPEG-Lossless, corresponds to frames encoded using Huffman, predictive sequential lossless encoding as defined by ISO DIS 10918-1 "Digital Compression and Coding of Continuous-tone Still Images". A data stream of JPEG Interchange Format (JIF) data is returned: all tables, compressed data, and so on are embedded in the data stream, all delineated by markers. This technique is not available in the R6 sample implementation of XIE.

interleave determines whether all bands of a triple band image will be interleaved within a single encoded stream or whether three separate encoded streams will be produced. One of the following standard interleave values can be assigned to *interleave*:

xieValBandByPixel

xieValBandByPlane

For triple band data, <code>band_order</code> specifies the order in which the image bands were originally encoded. One of the following standard orientation values can be assigned to <code>band_order</code>:

xieValLSFirst xieValMSFirst

The least significant band of trichromatic data is the first band mentioned in the common name of the colorspace: red is the least significant band of RGB data. <code>band_order</code> specifies whether this band corresponds with the least significant or most significant image plane. Each plane is encoded from a separate data stream:

band	LSFirst	MSFirst
0	Red band	Blue band
1	Green band	Green band
2	Blue band	Red band

The arguments interleave and band order are ignored for single band images.

predictor is the predictor selection value (one per band). table is the lossless entropy encoding table (up to one per band). Specifying a table of length zero indicates that the server implementor should supply a table (for example, the example tables defined in ISO DIS 10918-1 "Digital Compression and Coding of Continuous-Tone Still Images").

Structures

XieTecEncodeJPEGLossless sets the structure field interleave to the value of the argument *interleave*; the structure field band_order to the value of the argument *band_order*; the structure field predictor to the values of the argument *predictor*; and the structure fields table, table_size to the values of the arguments *table*, *table size*.

```
typedef unsigned XieOrientation;
typedef struct {
   XieInterleave interleave:
   XieOrientation band order:
   unsigned char predictor[3]:
   char*table;
   unsigned int table size;
} XieEncode[PEGLosslessParam;
/* Definitions for Interleave */
#define xieValBandBvPixel
                                              1
#define xieValBandByPlane
                                              2
/* Definitions of Orientation Types */
#define xieValLSFirst
                                              1
#define xieValMSFirst
                                              2
```

See Also

Xie Flo Export Client Photo, Xie Flo Export Photomap, Xie Get Client Data

XieTecEncodeTIFF2

XIElib - Technique Functions

Name

XieTecEncodeTIFF2 - allocate and fill an XieEncodeTIFF2Param structure

Syntax

XieEncodeTIFF2Param *XieTecEncodeTIFF2 (encoded_order, radiometric) XieOrientation encoded_order; Bool radiometric;

Arguments

encoded_orderradiometricSpecifies the bit order of the encoded data.Specifies how "white runs" are decoded.

Returns

The XieEncodeTIFF2Param structure.

Description

XieTecEncodeTIFF2 allocates and returns a pointer to an XieEncodeTIFF2Param structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeTIFF2).

If insufficient memory is available, XieTecEncodeTIFF2 returns NULL. To free the memory allocated to this structure, use XFree.

TIFF-2 is modified Huffman compression as described in "TIFF Tag Image File Format", revision 6.0, draft 2, by Aldus Corporation (TIFF compression scheme 2).

radiometric specifies that image ones will be encoded as "white runs", or conversely, image zeros will be encoded as "white runs", if radiometric is False. encoded_order specifies the bit order for the encoded data. One of the following standard orientation values can be assigned to encoded_order:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

Structures

XieTecEncodeTIFF2 sets the structure field encoded_order to the value of the argument <code>encoded_order</code>; and the structure field radiometric to the value of the argument <code>radiometric</code>.

typedef unsigned XieOrientation;

```
typedef struct {
    XieOrientation encoded_order;
    Bool radiometric;
} XieEncodeTIFF2Param;

/* Definitions of Orientation Types */
#define xieValLSFirst 1
#define xieValMSFirst 2
```

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

XIElib - Technique Functions XieTecEncodeTIFFPackBits

Name

XieTecEncodeTIFFPackBits - allocate and fill an XieEncodeTIFFPackBitsParam structure

Syntax

XieEncodeTIFFPackBitsParam *XieTecEncodeTIFFPackBits (encoded_order) XieOrientation encoded_order;

Arguments

encoded order

Specifies the bit order of the encoded data.

Returns

The XieEncodeTIFFPackBitsParam structure.

Description

XieTecEncodeTIFFPackBits allocates and returns a pointer to an XieEncodeTIFFPackBitsParam structure. The returned structure represents the list of parameters required by the encode technique and may be used as the <code>encode_param</code> argument of XieFloExportClientPhoto and XieFloExportPhotomap (when the <code>encode_tech</code> argument is xieValEncodeTIFFPackBits).

If insufficient memory is available, XieTecEncodeTIFFPackBits returns NULL. To free the memory allocated to this structure, use XFree.

TIFF-PackBits is byte-oriented run-length encoding as described in "TIFF Tag Image File Format", revision 6.0, draft 2, by Aldus Corporation (TIFF compression scheme 32773).

encoded_order specifies the bit order of the encoded data. One of the following standard orientation values can be assigned to *encoded order*:

xieValLSFirst xieValMSFirst

The following table shows the encoded bit order of two bytes (within each byte the first encoded bit is "0", and the last is bit "7"):

LSFirst	MSFirst
76543210 76543210	01234567 01234567

Structures

XieTecEncodeTIFFPackBits sets the structure field encoded_order to the value of the argument *encoded order*.

typedef unsigned XieOrientation; typedef struct { XieOrientation encoded_order; } XieEncodeTIFFPackBitsParam;

/* Definitions of Orientation Types */	
#define xieValLSFirst	1
#define xieValMSFirst	2

See Also

XieFloExportClientPhoto, XieFloExportPhotomap, XieGetClientData

XIElib - Technique Functions XieTecGeomAntialiasByArea

Name

 $\label{lem:comparison} \mbox{XieTecGeomAntialiasByArea-allocate and fill an XieGeomAntialiasByAreaParam structure}$

Syntax

XieGeomAntialiasByAreaParam *XieTecGeomAntialiasByArea (simple) int simple;

Arguments

simple

Specifies the approximation form to use.

Returns

 $The \ Xie Geom Antialias By Area Param\ structure.$

Description

XieTecGeomAntialiasByArea allocates and returns a pointer to an XieGeomAntialiasByAreaParam structure. The returned structure represents the list of parameters required by the geometry technique and may be used as the <code>sample_param</code> argument of XieFloGeometry (when the <code>sample_tech</code> argument is <code>xieValGeomAntialiasByArea</code>).

If insufficient memory is available, XieTecGeomAntialiasByArea returns NULL. To free the memory allocated to this structure, use XFree.

Antialiasing techniques incorporate information from an "area" of pixels in the input image in order to produce each output pixel. This implies that line dropouts and other artifacts will occur less often, and the output image may have markedly better resemblance to the input image. The technique AntialiasByArea computes the output image by assigning to each output pixel the weighted average of the intensity values of input pixels that fall within its "area". That is, the four corners of the output pixel are projected back onto the input image.

If *simple* is zero (0), the size and shape of the "area" are determined by the parameters of the geometric transformation. The boundaries of the "area" may not fall on pixel boundaries and, in the case of nonorthogonal rotation of the image, "area" may not be rectangular. Partial input pixel values may have to be calculated: the antialias-by-area technique preserves shape but can be very slow computationally.

Because of the computational complexity of this method, two approximations are supported. If simple is nonzero, the pixels covered by the projected area will be averaged without regard to the relative amount of area that they contain: if they are touched by the area, they are included in a simple average. If simple is set to N, with N odd and greater than one $(3,5,7,\ldots)$, then only the center point of the output pixel is projected, and a simple average is taken of an N by N window centered on the projection. For best results, N should correspond roughly to the amount of scaling that will be done.

Structures

 ${\it Xie Tec Geom Antialias By Area \ sets \ the \ structure \ field \ simple \ to \ the \ value \ of \ the \ argument \ simple .}$

```
typedef struct {
   int simple;
} XieGeomAntialiasByAreaParam;
```

See Also

XieFloGeometry

Functions

XieTecGeomAntialiasByLowpass

Name

XieTecGeomAntialiasByLowpass - allocate and fill an XieGeomAntialiasByLowpassParam structure

Syntax

 $XieGeomAntialiasByLowpassParam *XieTecGeomAntialiasByLowpass (kernel_size) int kernel size;$

Arguments

kernel size

Specifies the size of the image kernel.

Returns

The XieGeomAntialiasByLowpassParam structure.

Description

XieTecGeomAntialiasByLowpass allocates and returns a pointer to an XieGeomAntialiasByLowpassParam structure. The returned structure represents the list of parameters required by the geometry technique and may be used as the <code>sample_param</code> argument of XieFloGeometry (when the <code>sample_tech</code> argument is xieValGeomAntialiasByLowpass).

If insufficient memory is available, XieTecGeomAntialiasByLowpass returns NULL. To free the memory allocated to this structure, use XFree.

Antialiasing techniques incorporate information from an "area" of pixels in the input image in order to produce each output pixel. This implies that line dropouts and other artifacts will occur less often, and the output image may have markedly better resemblance to the input image. The technique AntialiasByLowpass represents an approximation to antialias-by-area that can be faster, yet provides similar results. First, a low-pass filter is applied by passing an *nxn* boxcar kernel over the original input image. Output pixel values are then derived using a nearest neighbor sampling method that selects the value of the input pixel in the upper-left corner of the area mapped back from the output pixel.

The user is allowed to select the size of the image kernel via the <code>kernel_size</code> parameter. For best results, <code>kernel_size</code> should be chosen to correspond roughly to the amount of scaling that will be done. Note that the server chooses the best kernel for the appropriate size; the values used in the kernel are not alterable by the client application. Clients wishing to specify the kernel in more detail should use the convolve technique directly.

Structures

XieTecGeomAntialiasByLowpass sets the structure field kernel_size to the value of the argument *kernel size*.

```
typedef struct {
   int kernel_size;
```

 $\ \}\ Xie Geom Antialias By Lowpass Param;$

See Also

 $\it XieFloGeometry, XieFloConvolve, XieTecGeomAntialias By Area$

XIElib - Technique Functions

XieTecGeomGaussian

Name

XieTecGeomGaussian - allocate and fill an XieGeomGaussianParam structure

Syntax

XieGeomGaussianParam *XieTecGeomGaussian (sigma, normalize, radius, simple)

double sigma; double normalize; unsigned int radius; Bool simple;

Arguments

sigma Specifies the drop-off rate.

normalize Specifies a normalization constant.
radius Specifies the extent of computation.
simple Specifies the approximation form to use.

Returns

The XieGeomGaussianParam structure.

Description

XieTecGeomGaussian allocates and returns a pointer to an XieGeomGaussianParam structure. The returned structure represents the list of parameters required by the geometry technique and may be used as the <code>sample_param</code> argument of XieFloGeometry (when the <code>sample_tech</code> argument is xieValGeomGaussian).

If insufficient memory is available, XieTecGeomGaussian returns NULL. To free the memory allocated to this structure, use XFree.

A Geometry element can be visualized as stepping through each possible output pixel location in turn, and computing the location from which to obtain each input pixel value. Each pixel (x',y') in the output image is mapped to the coordinate location (x,y) in src by:

It is not unusual that the input location (x,y) so derived will be nonintegral and will not correspond exactly to a single pixel in the input image.

From sampling theory, a bandwidth limited continuous input image can be recovered perfectly (under certain conditions) from its sampled output by computing the convolution:

Here I(x,y) is the continuous image, i(m,n) the discrete sampled image, and h(u,v) is the impulse response function for an appropriate low-pass filter. The specific form of h(u,v) for a Gaussian impulse response function is given by:

The term is called the "normalization constant" and may be altered using the *normalize* parameter. The suggested value for (*sigma*, the drop-off rate) is 1. Note that all technique parameters must be chosen in concert

radius defines the extent of computation. A suggested value for radius is one, that is, only pixels within a distance of one in either the x or y direction are involved in the calculation.

For computational convenience, a simplified form of Gaussian interpolation is provided. If *simple* is True, the impulse-response function h(u,v) is:

The normalization factor N is defined by normalize. As with true Gaussian interpolation, the radius parameter is used to determine the number of pixels involved in the computation.

Structures

XieTecGeomGaussian sets the structure field sigma to the value of the argument *sigma*; the structure field normalize to the value of the argument *normalize*; the structure field radius to the value of the argument *radius*; and the structure field simple to the value of the argument *simple*.

```
typedef struct {
    float sigma;
    float normalize;
    unsigned int radius;
    Bool simple;
} XieGeomGaussianParam;
```

See Also

XieFloGeometry

XIElib - Technique Functions XieTecGeomNearestNeighbor

Name

 $\label{eq:compared} \begin{tabular}{ll} Xie Tec Geom Nearest Neighbor - allocate and fill an \\ Xie Geom Nearest Neighbor Param structure \\ \end{tabular}$

Syntax

XieGeomNearestNeighborParam *XieTecGeomNearestNeighbor (modify) unsigned int modify;

Arguments

modify

Specifies technique behavior on even boundaries.

Returns

 $The \ Xie Geom Near est Neighbor Param\ structure.$

Description

XieTecGeomNearestNeighbor allocates and returns a pointer to an XieGeomNearestNeighborParam structure. The returned structure represents the list of parameters required by the geometry technique and may be used as the <code>sample_param</code> argument of XieFloGeometry (when the <code>sample_tech</code> argument is xieValGeomNearestNeighbor).

If insufficient memory is available, XieTecGeomNearestNeighbor returns NULL. To free the memory allocated to this structure, use XFree.

A Geometry element can be visualized as stepping through each possible output pixel location in turn, and computing the location from which to obtain each input pixel value. Each pixel (x',y') in the output image is mapped to the coordinate location (x,y) in src by:

It is not unusual that the input location (x,y) so derived will be nonintegral and will not correspond exactly to a single pixel in the input image.

To illustrate NearestNeighbor technique, assume that the pixel grid locations P, Q, R, and S are integral. Pixel location X = (x,y)T, obtained from the mapping equation above, differs from P by fractional amounts s in the x direction and t in the y direction.

Let I(P) be the value of the input image at coordinate P, if P is within the image extent. Otherwise, let I(P) be *constant*, where *constant* is the pixel value passed to the Geometry element. A value of I(X) must be estimated from I(P), I(Q), I(R), and I(S). In nearest-neighbor sampling, we simply choose the image value from the discrete location closest to X. Thus,

```
if s < 1/2, t < 1/2, set I(X) = I(P), if s > 1/2, t < 1/2, set I(X) = I(Q), if s > 1/2, t > 1/2, set I(X) = I(R),
```

```
if s < 1/2, t > 1/2, set I(X) = I(S).
```

The behavior on even boundaries (s = 1/2 or t = 1/2) is determined by the *modify* parameter. One of the standard nearest neighbor modify values can be assigned to *modify*:

```
xieValFavorDown
xieValFavorUp
xieValRoundNW
xieValRoundNE
xieValRoundSE
xieValRoundSW
```

If modify is xieValFavorDown, all "less than" signs in the above are replaced with "less than" or "equal "signs. Thus, P would win all ties, S and Q would lose to P but win over R, and R would lose all ties. If modify is xieValFavorUp, then all greater than signs would be replaced with greater than or equals, and the opposite behavior would occur. Four additional options are provided. The xieValRoundxx options will always choose a specific integral pixel grid location; these are not strictly nearest neighbor algorithms but are available for computational/filtering convenience.

Structures

XieTecGeomNearestNeighbor sets the structure field modify to the value of the argument *modify*.

```
typedef struct {
    unsigned int modify;
} XieGeomNearestNeighborParam;
/* Definitions of NearestNeighbor Modify */
#define xieValFavorDown 1
#define xieValFavorUp 2
#define xieValRoundNW 3
#define xieValRoundNE 4
#define xieValRoundSE 5
#define xieValRoundSW 6
```

See Also

XieFloGeometry

XIElib - Technique Functions XieTecHistogramGaussian

Name

XieTecHistogramGaussian - allocate and fill an XieHistogramGaussianParam structure

Syntax

XieHistogramGaussianParam *XieTecHistogramGaussian (mean, sigma) double mean; double sigma;

Arguments

mean Specifies the center of the Gaussian probability density

function.

sigma Specifies the "spread" of the Gaussian probability

density function.

Returns

 $The \ Xie Histogram Gaussian Param \ structure.$

Description

XieTecHistogramGaussian allocates and returns a pointer to an XieHistogramGaussianParam structure. The returned structure represents the list of parameters required by the match-histogram shape technique and may be used as the <code>shape_param</code> argument of XieFloMatchHistogram (when the <code>shape</code> argument is xieValHistogramGaussian).

If insufficient memory is available, XieTecHistogramGaussian returns NULL. To free the memory allocated to this structure, use XFree.

The Gaussian match-histogram shape technique specifies that the output image is to have a histogram that approximates a Gaussian probability density. The supplied parameters are used to generate a Gaussian probability density function centered around the *mean* level with a "spread" specified by *sigma*:

Structures

XieTecHistogramGaussian sets the structure field mean to the value of the argument *mean*; and the structure field sigma to the value of the argument *sigma*.

```
typedef struct {
    float mean;
    float sigma;
} XieHistogramGaussianParam;
```

See Also

 $\it Xie Flo Match Histogram$

XIElib - Technique Functions XieTecHistogramHyperbolic

Name

XieTecHistogramHyperbolic - allocate and fill an XieHistogramHyperbolicParam structure

Syntax

XieHistogramHyperbolicParam *XieTecHistogramHyperbolic (constant, shape_factor)
double constant;
Bool shape factor;

Arguments

constant Specifies a value used to generate a hyperbolic

probability density function

shape factor Specifies the relationship between the histogram shape

and image levels.

Returns

The XieHistogramHyperbolicParam structure.

Description

XieTecHistogramHyperbolic allocates and returns a pointer to an XieHistogramHyperbolicParam structure. The returned structure represents the list of parameters required by the match-histogram shape technique and may be used as the <code>shape_param</code> argument of XieFloMatchHistogram (when the <code>shape</code> argument is xieValHistogramHyperbolic).

If insufficient memory is available, XieTecHistogramHyperbolic returns NULL. To free the memory allocated to this structure, use XFree.

The hyperbolic match-histogram shape technique specifies that the output image is to have a histogram that approximates a hyperbolic probability density.

constant is used to generate a hyperbolic probability density function:

shape_factor should be specified as False if the histogram shape represents decreasing values for higher *levels* or True if the shape represents increasing values for higher *levels*.

Structures

XieTecHistogramHyperbolic sets the structure field constant to the value of the argument *constant*; and the structure field shape_factor to the value of the argument *shape_factor*.

```
typedef struct {
    float constant;
    Bool shape_factor;
} XieHistogramHyperbolicParam;
```

See Also

 $\it Xie Flo Match Histogram$

XIElib - Technique

Functions

XieTecWhiteAdjustCIELabShift

Name

XieTecWhiteAdjustCIELabShift - allocate and fill an XieWhiteAdjustCIELabShiftParam structure

Syntax

XieWhiteAdjustCIELabShiftParam *XieTecWhiteAdjustCIELabShift (white_point) XieConstant white point;

Arguments

white point

Specifies the white point of the (source or output) data.

Returns

The XieWhiteAdjustCIELabShiftParam structure.

Description

XieTecWhiteAdjustCIELabShift allocates and returns a pointer to an XieWhiteAdjustCIELabShiftParam structure. The returned structure represents the list of parameters required by the WhiteAdjust technique and may be used as the white adjust_param argument of XieTecRGBToCIELab, XieTecRGBToCIEXYZ, XieTecCIELabToRGB, and XieTecCIEXYZToRGB (when the white_adjust_tech argument is xieValWhiteAdjustCIELabShift).

If insufficient memory is available, XieTecWhiteAdjustCIELabShift returns NULL. To free the memory allocated to this structure, use XFree.

White point correction can be used to ensure that white "looks" white, or it can be used to change the overall tint of an image.

The CIELabShift WhiteAdjust technique specifies that white point correction is to be accomplished by adding the white point displacement to the *ab* plane in the CIELab colorspace. The *white_point* is specified using CIEXYZ encodings. If the WhiteAdjust technique is used with a color conversion technique that converts from RGB, *white_point* specifies the desired white point of the output data; if the conversion is to RGB, *white_point* specifies the white point of the source data.

Structures

XieTecWhiteAdjustCIELabShift sets the structure field white_point to the value of the argument *white_point*.

typedef float XieConstant[3];
typedef unsigned XieWhiteAdjustTechnique;
typedef struct {
 XieConstant white_point;
} XieWhiteAdjustCIELabShiftParam;

See Also

XIElib - Free Functions

XieFreeTechniques

Name

XieFreeTechniques - free memory allocated for a list of techniques

Syntax

```
void XieFreeTechniques (techs, count)
    XieTechnique *techs;
    unsigned int count;
```

Arguments

techs Specifies the list of techniques to be freed.

count Specifies the number of items in the list of techniques to

be freed.

Description

XieFreeTechniques frees the memory previously allocated for *techs*. Care should be taken that the argument pair *techs/count* match an argument pair *techniques ret/ntechniques ret* returned from XieQueryTechniques.

See XieQueryTechniques for a description of the XieTechnique structure.

Structures

```
typedef unsigned XieTechniqueGroup;
typedef struct {
   Bool needs_param;
   XieTechniqueGroup group;
   unsigned int number;
   unsigned int speed;
   char *name;
} XieTechnique;
```

See Also

XieQueryTechniques

XieFreePhotofloGraph

Name

XieFreePhotofloGraph - free memory allocated for an array of XiePhotoElement structures

Syntax

```
void XieFreePhotofloGraph (elements, count)
   XiePhotoElement *elements;
   unsigned int count;
```

Arguments

elements Specifies the array of XiePhotoElement structures to be

freed.

count Specifies the number of XiePhotoElement structures in

the array.

Description

XieFreePhotofloGraph frees the specified array of XiePhotoElement structures.

Care should be taken that the argument pair *elements/count* match a returned value (an array of XiePhotoElement structures) and argument *count* from a call to XieAllocatePhotofloGraph.

Technique parameters are not freed by using XieFreePhotofloGraph. Most of the technique parameters, with the exception of the JPEG baseline and JPEG lossless encode techniques, which are allocated using XIElib convenience functions are freed using XFree. This is so the client can reuse technique parameters between photoflos.

Structures

```
typedef struct {
    int elemType;
    /* union of ALL element types */
    union {
        ...
        ...
    } data;
} XiePhotoElement;
```

See Also

 $\label{locatePhotofloGraph} Xie Allocate Photoflo Graph, Xie Create Photoflo, Xie Execute Photoflo, Xie Execute Immediate$

XIElib - Free Functions XieFreeEncodeJPEGBaseline

Name

 $\label{eq:code_period} \mbox{XieFreeEncodeJPEGBaseline - free the memory allocated to the structure} \\ \mbox{XieEncodeJPEGBaselineParam}$

Syntax

```
void XieFreeEncodeJPEGBaseline (param)
XieEncodeJPEGBaselineParam *param
```

Arguments

param

Specifies a pointer to the structure that is to be freed.

Description

XieFreeEncodeJPEGBaseline (rather than XFree) should be used to free the memory allocated by XieTecEncodeJPEGBaseline.

Structures

```
typedef struct {
    XieInterleave interleave;
    XieOrientation band_order;
    unsigned char horizontal_samples[3];
    unsigned char vertical_samples[3];
    char *q_table;
    unsigned int q_size;
    char *ac_table;
    unsigned int ac_size;
    char *dc_table;
    unsigned int dc_size;
}
```

See Also

XieTecEncodeJPEGBaseline

XIElib - Free Functions XieFreeEncodeJPEGLossless

Name

 $\label{eq:conditional} Xie Free Encode JPEGLossless-free \ the \ memory \ allocated \ to \ the \ structure \\ Xie Encode JPEGLossless Param$

Syntax

```
void XieFreeEncodeJPEGLossless (param)
XieEncodeJPEGLosslessParam *param;
```

Arguments

param

Specifies a pointer to the structure that is to be freed.

Description

XieFreeEncodeJPEGLossless (rather than XFree) should be used to free the memory allocated by XieTecEncodeJPEGLossless.

Note that the JPEG Lossless technique is not available in the R6 sample implementation of XIE.

Structures

```
typedef struct {
    XieInterleave interleave;
    XieOrientation band_order;
    unsigned char predictor[3];
    char *table;
    unsigned int table_size;
} XieEncodeJPEGLosslessParam;
```

See Also

XieTecEncodeJPEGLossless

XieFreePasteUpTiles

Name

XieFreePasteUpTiles - free the memory allocated to the tiles field of a PasteUp structure

Syntax

```
void XieFreePasteUpTiles (element)
XiePhotoElement *element;
```

Arguments

element

Specifies the XiePhotoElement structure to use.

Description

XieFreePasteUpTiles frees the memory allocated to the tiles field in the specified PasteUp member structure; after the memory has been freed, the field value is set to NULL.

Structures

```
typedef struct {
    int elemType;
    union {
        ...
        struct {
            unsigned int width;
            unsigned int height;
            XieConstant constant;
            XieTile *tiles;
            unsigned int tile_count;
        } PasteUp;
        ...
    } data;
} XiePhotoElement;
```

See Also

XieFloPasteUp

XIElib Events ColorAlloc

Description

The client is notified that a ConvertToIndex element has completed color allocation, but has produced a result of lesser fidelity than was requested using the technique that was specified for the ConvertToIndex element.

The structure fields name_space, flo_id, src, and elem_type identify the photoflo and specific ConvertToIndex element from which the ColorAlloc event originated. The structure field time is the server time when the ColorAlloc event occurred, in milliseconds. The structure field color_list is the color list resource that received the allocated colors. The structure field color_alloc_technique is the ColorAlloc technique specified to the ConvertToIndex element. The structure field color_alloc_data can be used for other information that is specific to the ColorAlloc technique.

Structures

```
/* ColorAlloc Event Code */
#define xieEvnNoColorAlloc
                                             0
typedef struct {
   int type;
   unsigned long serial;
   Bool send event;
   Display *display;
   unsigned long name space;
   Time time:
   unsigned long flo id;
   XiePhototag src;
   unsigned int elem type;
   XieColorList color list:
   XieColorAllocTechnique color alloc technique;
   unsigned long color alloc data;
} XieColorAllocEvent;
```

See Also

XieFloConvertToIndex, XieTecColorAllocAll

Description

A DecodeNotify event notifies the client that anomalies were encountered while decoding a compressed image (see the *notify* arguments of XieFloImportClientPhoto and XieFloImportPhotomap). Either an error has been encountered while decoding an image, or the image data received does not satisfy the expected dimensions.

The structure fields name_space, flo_id, src, and elem_type identify the photoflo and element from which the DecodeNotify event originated. The structure field time is the server time when the DecodeNotify event occurred, in milliseconds. The structure field band_number associates the event with a specific band of the image. The structure field decode_technique is the Decode technique being used. The structure fields width and height are the dimensions discovered while decoding the data. The structure field aborted is True if decoding was aborted, or False if recovery was possible.

Recovery from a decode error may result in some missing or garbled image data. This may also cause the height of the decoded data to be less than was expected. If the structure fields width or height do not match the width and height specified to XieFloImportClientPhoto, the image data is clipped or padded (with zeros), as required, to enforce the XieFloImportClientPhoto specified dimensions.

Structures

```
/* DecodeNotify Event Code */
                                            1
#define xieEvnNoDecodeNotify
typedef struct {
   int type:
   unsigned long serial;
   Bool send event;
   Display *display;
   unsigned long name space;
   Time time;
   unsigned long flo id;
   XiePhototag src;
   unsigned int elem type:
   XieDecodeTechnique decode technique;
   Bool aborted:
   unsigned int band number;
   unsigned long width;
   unsigned long height;
} XieDecodeNotifyEvent;
```

See Also

XieFloImportClientPhoto, XieFloImportPhotomap

Description

The client is notified that an ExportClient element has data available (see the *notify* argument of the applicable XieFloExportClient... function). If *notify* was specified as xieValFirstData, this event will be sent only the first time data become available from the ExportClient element. Otherwise (that is, xieValNewData was specified), this event will be generated each time the amount of data available changes from zero to nonzero.

The structure fields name_space, flo_id, src, and elem_type identify the photoflo and specific ExportClient element from which the ExportAvailable event originated. The structure field time is the server time when the ExportAvailable event occurred, in milliseconds. The structure field band_number associates the event with a specific band of the image or LUT. The structure field data is information specific to elem_type (for example, the number of LUT entries or ROI rectangles available).

Where there is a single ExportClient element, the client can just read bytes or be event-driven. For photoflos containing multiple ExportClient elements, the client should be event-driven.

Structures

```
/* ExportAvailable Event Code */
#define xieEvnNoExportAvailable
                                             2
typedef struct {
   int type;
   unsigned long serial;
   Bool send event;
   Display *display;
   unsigned long name space;
   Time time:
   unsigned long flo id;
   XiePhototag src;
   unsigned int elem type;
   unsigned int band number:
   unsigned long data[3];
} XieExportAvailableEvent;
```

See Also

 $\label{linear_cont} XieFloExportClientHistogram, XieFloExportClientLUT, XieFloExportClientPhoto, XieFloExportClientROI$

XIElib Events

Description

The client is notified when an ImportDrawable or ImportDrawablePlane element encounters obscured regions in a Window that cannot be retrieved from backing store (see the *notify* argument of the import element routine). A separate ImportObscured event is returned for each affected region.

The structure fields name_space, flo_id, and src identify the photoflo and the specific import element from which the ImportObscured event originated. The structure field time is the server time when the ImportObscured event occurred, in milliseconds. The structure field window identifies the Window. The obscured region of the window is specified by the structure fields x, y, width, and height.

Note: image data within obscured regions will be populated with the *fill* argument supplied to the import element.

Structures

```
/* ImportObscured Event Code */
#define xieEvnNoImportObscured
                                             3
typedef struct {
   int type;
   unsigned long serial;
   Bool send event;
   Display *display;
   unsigned long name space;
   Time time:
   unsigned long flo id;
   XiePhototag src;
   unsigned int elem type;
   Window window;
   int x:
   int v;
   unsigned int width;
   unsigned int height;
} XieImportObscuredEvent;
```

See Also

XieFloImportDrawable, XieFloImportDrawablePlane

PhotofloDone

XIElib Events

Description

A PhotofloDone event notifies the client that a photoflo has left the active state. It is enabled by the *notify* argument of XieExecutePhotoflo or XieExecuteImmediate.

The photoflo from which the PhotofloDone event originated is identified by the structure fields name_space and flo_id. The structure field time is the server time when the PhotofloDone event occurred, in milliseconds. The reason the photoflo left the active state is indicated by the structure field type.

If the Photoflo terminated because of an error condition, the details concerning the error have preceded this event in an error message.

Structures

```
/* PhotofloDone Event Code */
#define xieEvnNoPhotofloDone 4

typedef struct {
    int type;
    unsigned long serial;
    Bool send_event;
    Display *display;
    unsigned long name_space;
    Time time;
    unsigned long flo_id;
} XiePhotofloDoneEvent;
```

See Also

XieExecuteImmediate, XieExecutePhotoflo

XIElib Errors

Resource Errors

The following error codes are allocated from the extension error space to provide for the errors returned by ${\rm XIE}$:

Error	Cause
xieErrNoColorlist	The value for a <i>color_list</i> argument does not name a defined color list.
xieErrNoLUT	The value for a lut argument does not name a defined LUT.
xieErrNoPhotoflo	The value for a <i>photoflo</i> argument does not name a defined photoflo.
xieErrNoPhotomap	The value for a <i>photomap</i> argument does not name a defined photomap.
xieErrNoPhotospace	The value for a <i>photospace</i> argument does not name a defined photospace.
xieErrNoROI	The value for a <i>roi</i> argument does not name a defined ROI.
xieErrNoFlo	An error has been detected while defining, executing, or accessing a photoflo (see Photoflo Errors).

 $\rm XIE$ also uses the core protocol BadAccess, BadAlloc, BadIDChoice, BadLength, BadRequest, and BadValue errors.

XIElib Errors

Photoflo Errors

If an error is detected while defining, executing, or accessing a photoflo, an xieErrNoFlo... error is returned. This single error code is allocated from the extension error space for all photoflo related errors. The following subcodes are defined to provide the details of the error:

Error	Cause
xieErrNoFloAccess	Attempt to execute, modify, or redefine an active photoflo <i>or</i> attempt to Get/Put client data from/to an inactive photoflo.
xieErrNoFloAlloc	Insufficient resources (for example, memory).
xieErrNoFloColormap	An unknown Colormap has been specified.
xie ErrNo Flo Color List	An unknown color list has been specified.
xieErrNoFloDomain	Invalid domain phototag: - source data is not a list-of-rectangles or control-plane or
' E M EL D. 11	- specified nonzero on a DIS server.
xieErrNoFloDrawable	An unknown Drawable has been specified.
xieErrNoFloElement	An unknown element type has been specified, or invalid element type for request, or attempt to change or add an element type.
xieErrNoFloGC	An unknown GContext has been specified.
xieErrNoFloID	Invalid executable: - an unknown photoflo has been specified <i>or</i> - an unknown photospace has been specified.
xieErrNoFloLength	An element was received with the incorrect number of bytes.
xieErrNoFloLUT	An unknown LUT has been specified.
xieErrNoFloMatch	Some argument or pair of arguments has the correct type and range, but it fails to match in some other way required by the element.
xie ErrNo Flo Operator	An unknown operator has been specified.
xie Err No Flo Photomap	An unknown photomap has been specified.
xieErrNoFloROI	An unknown ROI has been specified.
xieErrNoFloSource	An invalid phototag has been specified: - zero, but a phototag is required, <i>or</i> - downstream from the particular element, <i>or</i> - beyond the bounds of the photoflo.
xieErrNoFloTechnique	An unknown technique has been specified , or invalid technique specific-parameters have been specified, or the wrong number of technique-specific parameters have been given.
xieErrNoFloValue	Some numeric value falls outside of the range of values accepted by the element.

 $\begin{tabular}{ll} {\bf xieErrNoFloImplementation} & {\bf Some aspect of a request is not implemented} \\ & {\bf by the server: the client should be prepared to receive} \\ & {\bf and handle this error.} \end{tabular}$

Structures

/* Definition of Error Codes */	
#define xieErrNoColorList	0
#define xieErrNoLUT	1
#define xieErrNoPhotoflo	2
#define xieErrNoPhotomap	3
#define xieErrNoPhotospace	4
#define xieErrNoROI	5
#define xieErrNoFlo	6
/* Definitions of Flo Error (Sub-) Codes */	
#define xieErrNoFloAccess	1
#define xieErrNoFloAlloc	2
#define xieErrNoFloColormap	3
#define xieErrNoFloColorList	4
#define xieErrNoFloDomain	5
#define xieErrNoFloDrawable	6
#define xieErrNoFloElement	7
#define xieErrNoFloGC	8
#define xieErrNoFloID	9
#define xieErrNoFloLength	10
#define xieErrNoFloLUT	11
#define xieErrNoFloMatch	12
#define xieErrNoFloOperator	13
#define xieErrNoFloPhotomap	14
#define xieErrNoFloROI	15
#define xieErrNoFloSource	16
#define xieErrNoFloTechnique	17
#define xieErrNoFloValue	18
#define xieErrNoFloImplementation	19